

---

# **pymusepipe Documentation**

***Release 2.25.4***

**Eric Emsellem**

**Jul 24, 2023**



# CONTENTS

<b>1</b>	<b>Contents</b>	<b>3</b>
1.1	Welcome . . . . .	3
1.2	Install . . . . .	4
1.3	Getting Started . . . . .	5
1.4	Alignment . . . . .	8
1.5	Targets and Mosaicking . . . . .	9
1.6	Convolution . . . . .	9
1.7	PHANGS pipeline example . . . . .	9
1.8	License . . . . .	9
1.9	Contributors . . . . .	10
1.10	Changelog . . . . .	10
1.11	pymusepipe . . . . .	10
<b>2</b>	<b>Indices and tables</b>	<b>81</b>
	<b>Python Module Index</b>	<b>83</b>



This is the documentation of **pymusepipe**.



## CONTENTS

### 1.1 Welcome

Pymusepipe is a Python package which serves as a wrapper around the main processing steps of the MUSE data reduction pipeline (Weilbacher et al. 2019). Pymusepipe includes a simple data organiser and prescriptions for the structure of the data files (but no database per se), a wrapper around the main functionalities of MUSE data reduction pipeline, accessed via [EsoRex](#) command-line recipes, to remove the instrumental signatures. Pymusepipe additionally provides a set of modules supporting the alignment, mosaicking, two-dimensional and three-dimensional convolution.

pymusepipe is also made for multi-pointing mosaics and multi-targets surveys as it will process targets automatically when provided a specific dictionary of which target and which pointings to consider.

A description of the pipeline and its usage to reduce data from the PHANGS-MUSE survey are presented in Emsellem et al. (2022)

---

#### Contact

The pymusepipe module is maintained by Eric Emsellem. contact via

---

**Attention:** Please do not forget to cite Emsellem et al. (2022) and the MUSE data reduction pipeline paper (Weilbacher et al. 2019) if you make use of pymusepipe in your work. In particular, we suggest you add the following text (or equivalent) to the data reduction section of your work.

*The dataset was reduced using recipes the MUSE data processing pipeline software (Weilbacher et al. 2019). All recipes were executed with ESOREX commands, wrapped around using the dedicated python package pymusepipe (Emsellem et al. 2022).*

#### 1.1.1 GitHub Repository

You can access the source code of pymusepipe and its previous releases directly in its official GitHub repository <https://github.com/emsellem/pymusepipe>.

## 1.2 Install

### 1.2.1 Prerequisites

Pymusepipe assumes you have a working installation of ESOREX (i.e. that you have a working MUSE data reduction pipeline installation) and likwid-pin. The installation of these components is not covered here but can be found in the [MUSE Pipeline User Manual](#).

Pymusepipe uses [Python 3](#) and is not compatible with Python 2. It requires a number of standard python packages including:

- **numpy**
- **scipy**
- **matplotlib**
- **astropy**
- **mpdaf** a utility package to process and analyse datacubes, and more specifically MUSE cubes, images and spectra developed by the MUSE GTO-CRAL Team.

In addition some packages are needed to access specific functionality:

- **pypher** to use the convolution package of pymusepipe
- **spacepylot** to use the automatic alignment module

### 1.2.2 Installation

You can install this package via pypi via a simple:

```
pip install pymusepipe
```

You can obviously also install it by cloning it from github, or downloading the source (from github) and do something like:

```
python setup.py develop
```

The “develop” option is recommended as it actually does not copy the files in your system but just creates a link. In that way you can easily update the source software without reinstalling it. The link will directly use the source which has been updated.

The other option is to use the standard “install” option:

```
python setup.py install
```



## 1.3 Getting Started

### 1.3.1 Basic Usage - Dealing with OBs, individually

The pymusepipe wrapper is meant to provide the user with a simple way to run the MUSE pipeline.

Only three steps are needed:

1. preparing the data (download),
2. preparing the configuration files (templates are provided),
3. using the code (a few lines at most).

I recommend to use `Ipython` as an environment, possibly via a `screen` or `tmux` which would allow you to disconnect from the server that actually runs the commands.

### 1.3.2 Step 1: Preparing your data

The first thing to do is to prepare the folder structure to welcome your MUSE datasets.

Imagine you have:

- a target or field named e.g. `NGC1000`.
- several **datasets**. In the simplest cases this corresponds to data from one MUSE Observing Block (OB), including all the calibration and science object raw data files, as downloaded from the ESO archive. In practice pymusepipe will also reduce several OBs, provided all the necessary calibrations are available. Some functionality requires a distinction between **dataset** and **pointing**. This distinction is described in *Targets and Mosaicking*.

Then under your data root folder `<my_data_folder>` create the following folder structure:

```
<my_data_folder>/NGC1000
  ./OB001
    ./Raw
  ./OB002
    ./Raw
  ./OB003
    ./Raw
```

Each dataset, or OB for short, has a Raw folder.

The next step is to download your MUSE data (including raw calibrations) from the ESO web site, and put all the raw files (in fits or fits.gz format) into each individual Raw folders, associated with the right dataset.

### 1.3.3 Step 2: Preparing your configuration files

pymusepipe only needs two configurations ascii files:

1. `calib_tables.dic`, which contains a series of file names associated with muse static calibration files and other configuration files (e.g. filter lists). Most names are self-explanatory. These include:
  - `geo_table` and `astro_table`: static files, time dependent geometry files can be specified (see `rc.dic`).
  - `badpix_table`, `vignetting_mask`, `std_flux_table`, `extinct_table`, `line_catalog`, statical calibrations provided with the MUSE pipeline, no need to change these.
  - `filter_list` : used in case you wish to provide your own. Note that the file it needs to follow the MUSE standard for such a table.

2. `rc.dic`, which provides the root folders for the static calibration files and for your datasets.

- *root* provides the root folder for your data. For Target NGC1000, and OB 1, the Raw data will be looked for in *root*/NGC1000/OB001/Raw.
- *musecalib* should contain the standard MUSE calibration files. These are distributed in the MUSE pipeline installation in a “muse-calib-x.x.x/cal” folder.
- *musecalib\_time*: time dependent geometry and astrometry files (the correspondence between observing run dates and specific files are hard-coded into pymusepipe).

Examples of such files are provided in the `config_templates` folder of the pymusepipe package.

### 1.3.4 Step 3: Running the pipeline

Here is an example of how to run the pipeline to reduce a single OB (dataset):

```
# Import the modules
import pymusepipe as pmp
from pymusepipe import musepipe

# define the paths to the two configuration files
rcfile = "my_data/MUSE/Config/rc.dic"
calfile = "my_data_MUSE/Config/calib_tables.dic"

# Initialisation of the python - MusePipe Class - structure
mypipe = musepipe.MusePipe(targetname="NGC1000", dataset=1, rc_filename=rcfile,
                           cal_filename=calfile, log_filename="NGC1000_version01.log",
                           fakemode=False, overwrite_astropy_table=True,
                           filter_list="white,Cousins_R",
                           filter_for_alignment="Cousins_R")

# Launching the pipeline
mypipe.run_recipes()
```

That's it! Your data has now been reduced!

Some explanation may be needed to understand what is happening:

- `targetname`: is just the name of the target, used to decided where the data will be
- `dataset`: the number of the OB that will be used, namely “OB001” etc.
- `logfile`: name of the logging file.
- `fakemode`: you can set this to True if you just wish to initialise things without actually running any recipes. The pipeline will only set things up but if you run any recipes will only “fake” them (not launch any esorex command, only spitting the log out)
- `filter_list`: list of filter names to use to reconstruct images when building up cubes. This should be part of the `filter_list` fits table provided (see `calib_tables` config file).
- `filter_for_alignment`: specific filter name used for alignment between exposures.

Other options can be useful:

- `musemode`: this is by default `WFM_NOAO_N` which is the most often used MUSE mode. This will filter out exposures not compatible with the given mode.
- `reset_log`: will reset the log file. By default it is False, hence new runs will be appended.

- `overwrite_astropy_table`: by default this is False. If True, new runs will rewrite the Astropy output tables.
- `time_astrometry``: by default it is False, meaning the pipeline will try to detect a GEOMETRY and ASTROMETRY Files delivered with the Rawfiles by ESO. If set to True, it will use the time dependent astro/geo files provided by the GTO Team but you would need to make these available on your system. Hence I would recommend to keep the default (False).

### 1.3.5 Under the hood of `run_recipes`

`run_recipes()` launches a default set of functions listed below:

```
# generate the master bias using the muse_bias esorex recipe
mypipe.run_bias()
# generate the master flat using the muse_flat esorex recipe
mypipe.run_flat()
# generate the wavelength calibration using the muse_wavecal esorex recipe
mypipe.run_wave()
# generate the lsf using the muse_lsf esorex recipe
mypipe.run_lsf()
# generate the illumination correction using the muse_lsf esorex recipe
mypipe.run_twilight(illum=True)
# process individual exposures to remove the instrumental signature usign the muse_
↳ scibasic
# esorex recipes. It runs on both the object, standard star and sky exposures
mypipe.run_scibasic_all(illum=True)
# generates the response function using the standard star observations and the muse_
↳ standard
# esorex recipe
mypipe.run_standard()
# uses the sky exposures to generate a sky spectrum
mypipe.run_sky(fraction=0.8)
# runs the esorex muse_scipost recipe individually on each object exposures generating
# a datacubes and image in the requested filter for each exposure.
# These images are then used for alignment.
mypipe.run_prep_align()
# runs the muse_exp_align recipe to generate an OFFSET_TABLE files containing the_
↳ astrometric
# shifts between individual exposures. Pymusepipe provides more refined options for this
mypipe.run_align_bydataset()
# ??
mypipe.run_align_bygroup()
# generates the final aligned datacubes for individual exposures using muse_scipost
mypipe.run_scipost_perexpo()
# generates the sky datacube
mypipe.run_scipost_sky()
# merge exposures in the final datacube
mypipe.combine_dataset()
```

Individual pipeline stages can be (re)run by calling any of the individual functions above. The order is important, as in any data reduction process

**Attention:** This pipeline flow closely mirrors the standard data reduction for MUSE data implemented by the e.g. EsoReflex workflow. Pymusepipe offers alternative recipes to perform alignment (*Alignment*) and mosaicking (*Targets and Mosaicking*). For best results, therefore, we do not recommend running the above workflow. Examples workflows are presented in *PHANGS pipeline example*.

### 1.3.6 Structure of the output

#### Folders

The structure of the output is driven by a set of folder names described in `pymusepipe.init_musepipe()` in a few dictionaries (`dic_input_folders()`, `dic_folders()`, `dic_folders_target()`). You can in principle change the names of the folders themselves, although it is not advisable.

The pipeline will create the folder structure automatically, checking whether the folders exist or not.

#### Log files

Two basic log files are produced: one is the Esorex output which will be stored in the “Esorex\_log” folder. The other one will be in the “Log” folder with the name provided at start: that one is like a shell script which can be used to rerun things directly via the command line. In the “Log” folder, there will also be, for each log file, a file “.out” and one with “.err” extensions, respectively including all the stdout and stderr messages. This may be useful to trace details in the data reduction and problems.

#### Astropy Tables

Each recipe will trigger the creation of a astropy Table. These are stored under “Astro\_Tables”. You can use these to monitor which files have been processed or used.

#### Sof files

Sof files are saved under the “Sof” directory for each esorex recipes used in the pipeline. These are useful to see exactly which files are processed by each esorex recipe.

#### Python structure

Most of the information you may need is actually stored in the python `pymusepipe.musepipe.MusePipe` class structure. More details to come.

## 1.4 Alignment

### 1.4.1 Limitations of run\_align recipes

The esorex implementation of the alignment procedure (implemented in the `pymusepipe.prep_recipes_pipe.PipePrep.run_align_bydataset()`) for multiple object exposures suffers from some severe limitations:

- It does not perform absolute astrometry, but merely fixes the astrometry of subsequent exposures to the WCS of the first one. This is problematic for comparison of MUSE data with external datasets.

- It works by finding and matching point sources across white light images from multiple exposures. This requires the images to contain a sufficient number of point sources. Moreover, in case of mosaics, it requires the *overlap region* between different MUSE pointings to contain a sufficient number of point sources. In practice, this requirement is very limiting.

Pymusepipe provides the `pymusepipe.align_pipe()` module to overcome both these limitations.

## 1.5 Targets and Mosaicking

tbw

## 1.6 Convolution

tbw

## 1.7 PHANGS pipeline example

tbw

## 1.8 License

MIT License

Copyright (c) [2019] [Eric Emsellem]

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED “AS IS”, WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

## 1.9 Contributors

- Eric Emsellem <eric.emsellem@eso.org>

## 1.10 Changelog

### 1.10.1 Version 2.9.9

- Cleaning the full version including Target Sample

### 1.10.2 Version 1.0

- First structure with MusePointing

## 1.11 pymusepipe

### 1.11.1 pymusepipe package

#### Submodules

#### pymusepipe.align\_pipe module

MUSE-PHANGS alignment module. This module can be used to align MUSE reconstructed images either with each others or using a reference background image. It spits the results out in a Fits table which can then be used to process and mosaic Muse PIXTABLES via the MUSE ESO pipeline. It includes a normalisation factor, an estimate of the background, as well as any potential rotation. Fine tuning can be done by hand by the user, using a set of reference plots.

```
class pymusepipe.align_pipe.AlignMuseDataset(name_reference, folder_reference=None,
                                              folder_muse_images=None, name_muse_images=None,
                                              sel_indices_images=None, median_window=10,
                                              subim_window=10, dynamic_range=10, border=10,
                                              hdu_ext=(0, 1), chunk_size=15, firstguess='crosscorr',
                                              **kwargs)
```

Bases: `object`

Class to align MUSE images onto a reference image.

```
apply_extra_offset_ima(nima=0, extra_pixel=None, extra_arcsec=None, extra_rotation=None,
                        **kwargs)
```

Shift image with index nima with the total offset after adding any extra given offset This does not return anything but could in principle if using the output of the self.shift

## Input

### **nima: int**

Index of image to consider

### **extra\_pixel: list of 2 floats**

Extra offsets (x,y) in pixels. If None, nothing is applied

### **extra\_arcsec: list of 2 floats**

Extra offsets (x,y) in arcsec if extra\_pixel is not provided If None, nothing is applied

### **extra\_rotation: float**

Rotation in degrees. If None, no new extra offset is applied

### **apply\_optical\_flow\_offset\_ima(nima=0)**

Transfer the value of the optical flow into the extra pixel

### **apply\_optical\_flow\_offset\_listima(list\_nima=None)**

Apply the optical flow offset as extra pixels offsets and rotation

## Input

### **list\_nima: list**

If None, will be initiliased to the default list of indices

**compare**(data1, data2, header=None, start\_nfig=1, nlevels=10, levels=None, convolve\_data1=0.0, convolve\_data2=0.0, showcontours=True, showcuts=True, shownormalise=True, showdiff=True, normalise=True, median\_filter=True, ncuts=5, percentage=5.0, suffix\_fig="", \*\*kwargs)

Compare the projected reference and MUSE image by plotting the contours, the difference and vertical/horizontal cuts.

### Parameters

- **data1** –
- **data2** (2d *np.array*s) – Array to compare
- **header** (*Header*) – If provided, will be use to get the WCS in the plots. Default is None (ignored).
- **polypar** (*ODR result*) – If None, it will be recalculated
- **showcontours** (*bool* [True]) –
- **showcuts** (*bool* [True]) –
- **shownormalise** (*bool* [True]) –
- **showdiff** (*bool* [True]) – All options corresponding to 1 specific plot. By default show them all (all True)
- **ncuts** (*int* [5]) – Number of vertical / horizontal cuts along the ratio between the 2 maps to be shown (“cuts”)
- **percentage** (*float* [5]) – Used to compute which percentile to show
- **start\_nfig** (*int* [1]) – Number of the matplotlib Figure to start with
- **nlevels** (*int* [10]) – Number of levels for the contour plots
- **levels** (*list of float* [None]) – Specific list of levels if any (default is None)

- **convolve\_data1** (*float* [0]) – If not 0, will convolve with a gaussian of that sigma
- **convolve\_data2** (*float* [0]) – If not 0, will convolve the reference image with a gaussian of that sigma
- **(bool)** (*savefig*) – If True, will save the figure into a png
- **suffix\_fig** (*str*) – Suffix name to add to the figure filenames
- **figures** (*Makes a maximum of 4*) –

**compare\_ima**(*nima=0, nima\_museref=None, convolve\_muse=0, convolve\_reference=0.0, \*\*kwargs*)

## Input

**nima: int**

Index of input image

**nima\_museref: int**

Index of second input image for the reference. Default is None, hence ignored and the default reference image will be used.

**convolve\_muse: float**

Sigma of the gaussian to convolve the input images. Default is 0 (no convolution)

**convolve\_reference: float**

Sigma of the gaussian to convolve the reference. Default is 0 (no convolution)

**threshold\_muse: float**

Minimum value to consider in the input images

## Creates

Plots which compare the two input datasets as defined by the indices

**find\_cross\_peak**(*muse\_hdu, rotation=0.0, threshold=None, \*\*kwargs*)

Aligns the MUSE HDU to a reference HDU

## Input

**muse\_hdu: astropy.io.fits hdu**

MUSE hdu file

**name\_musehdr: str**

name of the muse hdr to save

**rotation: float**

Angle in degrees (0).

**threshold: minimum flux to be used in the cross-correlation**

Flux below that value will be set to 0. Default is 0.

**returns**

- *xpix\_cross*
- **ypix\_cross** (*x and y pixel coordinates of the cross-correlation peak*)



**find\_cross\_peak\_ima**(*nima=0, threshold=None*)

Find the cross correlation peak and get the x and y shifts for a given image, given its index nima

### Input

**nima: int**

Index of the image

**threshold: float**

Minimum flux for the cross-correlation

**find\_cross\_peak\_listima**(*list\_nima=None, threshold=None*)

Run the cross correlation peaks on all MUSE images Derive the self.cross\_off\_pixel/arcsec parameters

### Input

**list\_nima: list**

list of indices for images to process Should be a list. Default is None and all images are processed

**threshold: float [None]**

minimum flux to be used in the cross-correlation Flux below that value will be set to 0.

**get\_imaref\_muse**(*muse\_hdu, rotation=0.0, \*\*kwargs*)

Returns the ref and input images on the same grid as the given input hdu assuming a given rotation

### Input

**muse\_hdu: HDU**

MUSE hdu file

**name\_musehdr: str**

name of the muse hdr to save

**rotation: float**

Angle in degrees (0).

**threshold: float**

Minimum flux to prepare the image (0).

### returns

- **ima\_ref, ima\_muse** (*arrays*) – Reprojected images
- *Note that the original images are saved in self.\_temp\_input\_origmuse and*
- *self.\_temp\_input\_origref when debug mode is on (self.\_debug)*

**get\_normfactor\_ima**(*nima=0, median\_filter=True, border=0, convolve\_muse=0.0, convolve\_reference=0.0, chunk\_size=10, \*\*kwargs*)

Get the normalisation factor for shifted and projected images. This function only consider the input image given by index nima and the reference image (after projection).

## Input

**nima: int**

Index of image to consider

**median\_filter: bool**

If True, will median filter

**convolve\_muse: float [0]**

Will convolve the image with index nima with a gaussian with that sigma. 0 means no convolution

**convolve\_reference: float [0]**

Will convolve the reference image with a gaussian with that sigma. 0 means no convolution

**border: int**

Number of pixels to crop

**threshold: float [None]**

Threshold for the input image flux to consider

**chunk\_size: int**

Size of chunks to consider for chunk statistics (polynomial normalisation)

**returns**

- **data** (*2d array*)
- **refdata** (*2d array*) – The 2 arrays (input, reference) after processing

**get\_shift\_from\_pcc**(*muse\_hdu, rotation=0.0, threshold=0.0, verbose=False, \*\*kwargs*)

Find a guess translation using PCC

## Input

**muse\_hdu: HDU**

MUSE hdu file

**rotation: float**

Angle in degrees (0).

**threshold: float**

Minimum flux to prepare the image (0).

**name\_musehdr: str**

Name of the muse hdr to save. Optional. Only operational if self.save\_hdr is True

**returns**

- *xpix\_pcc*
- *ypix\_pcc* *x and y pixel coordinates of the cross-correlation peak*

**get\_shift\_from\_pcc\_ima**(*nima=None, threshold=None, rotation=None, verbose=False*)

Run the PCC shift guess for image nima

## Input

**nima: int**

Index of image

**threshold: float [None]**

minimum value to be used in the phase cross-correlation Flux below that value will be set to 0.

**rotation: float**

If None, will take the init\_rotangle. Otherwise it will take the input value

**get\_shift\_from\_pcc\_listima**(*list\_nima=None, threshold=None, verbose=False*)

Run the PCC shift guess on a list of images given by a list of indices

## Input

**list\_nima: list of indices for images to process**

Should be a list. Default is None and all images are processed

**thhreshold: float [None]**

minimum value to be used in the phase cross-correlation Flux below that value will be set to 0.

**init\_guess\_offset**(*\*\*kwargs*)

Initialise first guess, either from cross-correlation (default) or from an Offset FITS Table

## Input

**firstguess: str**

If “crosscorr” uses cross-correlation to get the first guess of the offsets. If “fits” uses the input fits table.

**init\_optical\_flow\_hdu**(*muse\_hdu, rotation=0.0, threshold=None, guess\_translation=(0.0, 0.0), header=None, verbose=False, \*\*kwargs*)

Get the optical flow for this hdu

## Input

**muse\_hdu: HDU**

Muse HDU input

**rotation: float**

Input rotation

**threshold: float**

Minimum flux to consider in the image

**guess\_translation: tuple of 2 floats**

Guess offset in X and Y, e.g., (0., 0.)

**name\_musehdr: str**

Name of hdr in case those are saved (self.save\_hdr is True)

```
init_optical_flow_ima(nima=0, threshold=None, guess_offset_pixel=None, guess_offset_arcsec=None,  
                      guess_rotation=None, force_pcc_guess=False, verbose=False,  
                      provide_header=True, **kwargs)
```

Initialise the optical flow using the current image with index nima

### Input

**nima: int**

Index of image

**threshold: float**

Minimum flux to consider

```
init_optical_flow_listima(list_nima=None, **kwargs)
```

Initialise the optical flow on a list of images given by a list of indices

### Input

**list\_nima: list of indices for images to process**

Should be a list. Default is None and all images are processed

```
iterate_on_optical_flow_ima(nima=0, niter=5, verbose=False, use_rotation=True, **kwargs)
```

Iterate solution using the optical flow guess

### Input

**nima: int**

Index of image to consider

**niter: int**

Number of iterations

```
iterate_on_optical_flow_listima(list_nima=None, use_rotation=True, **kwargs)
```

Run the iteration for the optical flow on a list of images given by a list of indices

### Input

**list\_nima: list of indices for images to process**

Should be a list. Default is None and all images are processed

**niter: int**

Number of iterations. Optional. If not provided, will use the default in self.iterate\_on\_optical\_flow\_ima

```
list_states(nstate_max=None)
```

## Input

**offset\_and\_compare\_ima**(*nima=0, extra\_pixel=None, extra\_arcsec=None, extra\_rotation=None, \*\*kwargs*)

Run the offset and comparison for a given image number

## Input

**nima: int**

Index of the image to consider

**extra\_pixel: list of 2 floats**

Offsets in X and Y in pixels to add to the existing guessed offsets IMPORTANT NOTE: extra\_pixel will be considered first (before extra\_arcsec).

**extra\_arcsec: list of 2 floats**

Offsets in X and Y in arcsec to add to the existing guessed offsets. Ignored if extra\_pixel is given or None

**extra\_rotation: rotation in degrees**

Angle to rotate the image (in degrees). Ignore if None

## Additional arguments

**threshold: float [0]**

Threshold to consider when plotting the comparison

**plot (bool): if True, will plot the comparison**

**If not used, will use the default self.plot**

- flux comparison (1 to 1)
- Map of the flux ratio
- Contours of the two scaled maps
- Cuts of the division between the 2 maps

See also all arguments from self.compare

**open\_hdu()**

Open the HDU of the MUSE and reference images

**open\_offset\_table**(*name\_table=None*)

Read offset table from fits file

## Input

**name\_table: str**

Name of the input OFFSET table

**returns**

- **status** (*None if no table name is given, False if file does not*) – exist, True if it does
- **Table** (*the result of a `astropy.Table.read` of the fits table*)

**print\_images\_names()**

Print out the names of the images being considered for alignment

**print\_offsets\_and\_norms**(*filename='\_temp.txt', folder\_output\_file=None, overwrite=True*)

Save all offsets and norms into filename. By default, file will be overwritten.

## Input

**filename: str**

Name of file where the output will be written

**folder\_output\_file: str**

Name of output folder where the file will be written

**overwrite: bool**

Default is True

## Creates

Ascii file named via the filename input argument

**retrieve\_state**(*nstate=1*)

Retrieve the state with offset and background and norm factors

## Input

*nstate* = int default=1

**run\_optical\_flow**(*list\_nima=None, save\_plot=True, use\_rotation=True, verbose=False, \*\*kwargs*)

Run Optical flow, first with a guess offset and then iterating. The solution is saved as extra offset in the class, and a `op_plot` instance is created. If `save_plot` is True, it will save a set of default plots

## Input

**list\_nima: list**

List of indices. If None, will use the default list of all images

**save\_plot**

[bool] Whether to save the optical flow diagnostic plots or not.

**use\_rotation: bool**

True if you wish to have rotation. False otherwise

verbose: bool

**run\_optical\_flow\_ima**(nima=0, save\_plot=True, use\_rotation=True, verbose=False, \*\*kwargs)

Run Optical flow on image with index nima, first with a guess offset and then iterating. The solution is saved as extra offset in the class, and a op\_plot instance is created. If save\_plot is True, it will save a set of default plots

## Input

**nima: int**

Image index.

**save\_plot**

[bool] Whether to save the optical flow diagnostic plots or not.

**save\_fits\_offset\_table**(name\_output\_table=None, folder\_output\_table=None, overwrite=False, suffix="", save\_flux\_scale=True, save\_other\_params=True)

Save the Offsets into a fits Table

## Input

**folder\_output\_table: str [None]**

Folder of the output table. If None (default) the folder for the input offset table will be used or alternatively the folder of the MUSE images.

**name\_output\_table: str [None]**

Name of the output fits table. If None (default) it will use the one given in self.name\_output\_table

**overwrite: bool [False]**

If True, overwrite if the file exists

**suffix: str [“”]**

Suffix to be used to add to the input name. This is handy to just modify the given fits name with a suffix (e.g., version number).

**save\_flux\_scale: bool [True]**

If True, saving the flux in FLUX\_SCALE If False, do not save the flux conversion

**save\_other\_params: bool [True]**

If True, saving the background + rotation If False, do not save these 2 parameters.

### Creates

A fits table with the given name (using the suffix if any)

**save\_image**(*newfits\_name=None, nima=0*)

Save the newly determined hdu

### Input

**newfits\_name: str**

Name of the fits file to be used

**nima: int [0]**

Index of the image to save

### Creates

A new fits file

**save\_polypar\_ima**(*nima=0, beta=None*)

Saving the input values into the fixed arrays for the polynomial

### Input

beta: list/array of 2 floats

**save\_state**(*force\_nstate=None*)

Save the offset and background and normalisation to a given attribute defined by self.\_nstate

### Input

force\_nstate: int default=None

**show\_linearfit\_values**()

Print some information about the linearly fitted parameters pertaining to the normalisation.

**show\_norm\_factors**()

Print some information about the normalisation factors.

**show\_offset\_fromfits**(*name\_table=None*)

Print offset table from fits file



## Input

**name\_table:** str

Name of the input OFFSET table

**show\_offsets()**

Print out the offset from the Alignment class

**transfer\_extra\_to\_guess**(*transfer\_rotation=True*)

Transfer the values of the extra offset as a guess

**class** pymusepipe.align\_pipe.**OffsetState**(*nstate=1, info=None*)

Bases: `object`

A very simple class used to store the offsets

**pymusepipe.align\_pipe.align\_hdu**(*hdu\_target=None, hdu\_to\_align=None, target\_rotation=0.0, to\_align\_rotation=0.0, conversion\_factor=1.0, use\_mpdaf=False*)

Project the reference image onto the MUSE dataset Hidden function, as only used internally

## Input

**hdu\_target:** HDU [None]

Target hdu (on to which to project)

**hdu\_to\_align:** HDU [None]

Hdu to be aligned

**target\_rotation:** float [0]

Rotation angle in degrees of the target hdu

**to\_align\_rotation:** float [0]

Rotation angle in degrees of the to be aligned hdu

**conversion\_factor:** float

Factor to be applied to the to\_align hdu

**use\_mpdaf:** bool

If True, use mpdaf to project. This is not recommended. If False, use reproject. This is the recommended option (default)

**returns**

**hdu\_repr** – Reprojected HDU. None if nothing is provided

**rtype**

HDU

**pymusepipe.align\_pipe.arcsec\_to\_pixel**(*hdu, xy\_arcsec=(0.0, 0.0)*)

Transform from arcsec to pixel for the muse image using the hdu to extract the WCS, hence the scaling.

## Input

**hdu:** astropy hdu (fits)

Input hdu which includes a WCS

**xy\_arcsec:** list of 2 floats ([0,0])

Coordinates to transform from arcsec to pixel.

## returns

- **xpix, ypix** (*tuple or list of 2 floats*) – Pixel coordinates
- **See also** (*pixel\_to\_arcsec (align\_pipe.py)*)

```

pymusepipe.align_pipe.get_conversion_factor(input_unit, output_unit, filter_name='WFI',
dict_equiv={'DUPONT_R': [(Unit("erg / (Angstrom cm2
s)"), Unit("erg / (cm2 Hz s)"), <function
spectral_density.<locals>.f_la_to_f_nu>, <function
spectral_density.<locals>.f_la_from_f_nu>), (Unit("erg /
(cm2 Hz s)"), Unit("erg / (cm2 s)"), <function
spectral_density.<locals>.f_nu_to_nu_f_nu>, <function
spectral_density.<locals>.f_nu_from_nu_f_nu>),
(Unit("erg / (Angstrom cm2 s)"), Unit("erg / (cm2 s)"),
<function spectral_density.<locals>.f_la_to_la_f_la>,
<function spectral_density.<locals>.f_la_from_la_f_la>),
(Unit("ph / (Angstrom cm2 s)"), Unit("erg / (Angstrom cm2
s)"), <function
spectral_density.<locals>.phot_f_la_to_f_la>, <function
spectral_density.<locals>.phot_f_la_from_f_la>),
(Unit("ph / (Angstrom cm2 s)"), Unit("erg / (cm2 Hz s)"),
<function spectral_density.<locals>.phot_f_la_to_f_nu>,
<function
spectral_density.<locals>.phot_f_la_from_f_nu>),
(Unit("ph / (Angstrom cm2 s)"), Unit("ph / (cm2 Hz s)"),
<function
spectral_density.<locals>.phot_f_la_to_phot_f_nu>,
<function
spectral_density.<locals>.phot_f_la_from_phot_f_nu>),
(Unit("ph / (cm2 Hz s)"), Unit("erg / (cm2 Hz s)"),
<function spectral_density.<locals>.phot_f_la_to_f_la>,
<function
spectral_density.<locals>.phot_f_la_from_f_la>),
(Unit("ph / (cm2 Hz s)"), Unit("erg / (Angstrom cm2 s)"),
<function spectral_density.<locals>.phot_f_nu_to_f_la>,
<function
spectral_density.<locals>.phot_f_nu_from_f_la>),
(Unit("ph / (cm2 s)"), Unit("erg / (cm2 s)"), <function
spectral_density.<locals>.phot_f_la_to_f_la>, <function
spectral_density.<locals>.phot_f_la_from_f_la>),
(Unit("erg / (Angstrom s)"), Unit("erg / (Hz s)"), <function
spectral_density.<locals>.f_la_to_f_nu>, <function
spectral_density.<locals>.f_la_from_f_nu>), (Unit("erg /
(Hz s)"), Unit("erg / s"), <function
spectral_density.<locals>.f_nu_to_nu_f_nu>, <function
spectral_density.<locals>.f_nu_from_nu_f_nu>),
(Unit("erg / (Angstrom s)"), Unit("erg / s"), <function
spectral_density.<locals>.f_la_to_la_f_la>, <function
spectral_density.<locals>.f_la_from_la_f_la>), (Unit("ph /
(Angstrom s)"), Unit("erg / (Angstrom s)"), <function
spectral_density.<locals>.phot_f_la_to_f_la>, <function
spectral_density.<locals>.phot_f_la_from_f_la>),
(Unit("ph / (Angstrom s)"), Unit("erg / (Hz s)"), <function
spectral_density.<locals>.phot_f_la_to_f_nu>, <function
spectral_density.<locals>.phot_f_la_from_f_nu>),
(Unit("ph / (Angstrom s)"), Unit("ph"), <function
spectral_density.<locals>.phot_f_la_to_phot_f_nu>,
<function
spectral_density.<locals>.phot_f_la_from_phot_f_nu>),
(Unit("ph"), Unit("erg / (Hz s)"), <function
spectral_density.<locals>.phot_f_la_to_f_la>, <function
spectral_density.<locals>.phot_f_la_from_f_la>),
(Unit("ph"), Unit("erg / (Angstrom s)"), <function
spectral_density.<locals>.phot_f_nu_to_f_la>, <function
spectral_density.<locals>.phot_f_nu_from_f_la>),

```

Conversion of units from an input one to an output one

### Input

**input\_unit: astropy unit**

Input astropy unit to analyse

**output\_unit: astropy unit**

Astropy unit to compare to input unit.

**filter\_name: str, optional**

Name of the filter

**dict\_equiv: dict, optional**

Dictionary listing the equivalencies for various filters. Will be using it if the filter name is the key list to help with the conversion.

**returns**

**conversion**

**rtype**

astropy unit conversion

`pymusepipe.align_pipe.init_plot_optical_flow(opflow)`

Initialise the optical flow plot using the AlignmentPlotting

### Input

*opflow*: optical flow instance (see spacepyplot)

**rtype**

An optical flow plot instance

`pymusepipe.align_pipe.is_sequence(arg)`

Test if sequence and return the boolean result

**Parameters**

**arg** (*input argument*) –

**Returns**

**result**

**Return type**

boolean

`pymusepipe.align_pipe.pixel_to_arcsec(hdu, xy_pixel=(0.0, 0.0))`

Transform from arcsec to pixel for the muse image using the hdu to extract the WCS, hence the scaling.

## Input

**hdu:** astropy hdu (fits)

Input hdu which includes a WCS

**xy\_pixel:** tuple or list of 2 floats ((0,0))

Coordinates to transform from pixel to arcsec

### returns

- **xarc, yarc** (2 floats) – Arcseconds coordinates
- **See also** (*arcsec\_to\_pixel* (*align\_pipe.py*))

`pymusepipe.align_pipe.rotate_pixtable(folder=', name_suffix=', nifu=1, angle=0.0, **kwargs)`

Rotate a single IFU PIXTABLE\_OBJECT Will thus update the HIERARCH ESO INS DROT POSANG keyword.

## Input

**folder:** str

name of the folder where the PIXTABLE are

**name\_suffix:** str

name of the suffix to be used on top of PIXTABLE\_OBJECT

**nifu:** int

Pixtable number. Default is 1

**angle:** float

Angle to rotate (in degrees)

`pymusepipe.align_pipe.rotate_pixtables(folder=', name_suffix=', list_ifu=None, angle=0.0, **kwargs)`

Will update the derotator angle in each of the 24 pixtables Using a loop on rotate\_pixtable

Will thus update the HIERARCH ESO INS DROT POSANG keyword.

## Input

**folder:** str

name of the folder where the PIXTABLE are

**name\_suffix:** str

name of the suffix to be used on top of PIXTABLE\_OBJECT

**list\_ifu:** list[int]

List of Pixtable numbers. If None, will do all 24

**angle:** float

Angle to rotate (in degrees)

## pymusepipe.check\_pipe module

MUSE-PHANGS check pipeline module

```
class pymusepipe.check_pipe.CheckPipe(mycube='DATACUBE_FINAL.fits', pdf_name='check_pipe.pdf',
                                       pipe=None, standard_set=True, **kwargs)
```

Bases: [MusePipe](#)

Checking the outcome of the data reduction

```
check_given_images(suffix=None)
```

Check all images with given suffix

```
check_master_bias_flat()
```

Checking the Master bias and Master flat

```
check_quadrants()
```

Checking spectra from the 4 quadrants

```
check_sky_spectra(suffix)
```

Check all sky spectra from the exposures

```
check_white_line_images(line='Ha', velocity=0.0)
```

Building the White and Ha images and Adding them on the page

```
pymusepipe.check_pipe.print_plot(text)
```

## pymusepipe.combine module

MUSE-PHANGS combine module

```
class pymusepipe.combine.MusePointings(targetname=None, list_datasets=None, list_pointings=None,
                                       pointing_table=None, pointing_table_format='ascii',
                                       pointing_table_folder="", folder_config="", rc_filename=None,
                                       cal_filename=None, suffix="", name_offset_table=None,
                                       folder_offset_table=None, log_filename='MusePipeCombine.log',
                                       verbose=True, debug=False, **kwargs)
```

Bases: [SofPipe](#), [PipeRecipes](#)

Class for a set of MUSE Pointings which can be covering several datasets. This provides a set of rules and methods to access the data and process them.

```
assign_pointing_table(input_table=None, folder="", table_format='ascii')
```

Assign the pointing table as provided. If not provided it will create one from the pixtable list

### Input

input\_table: str, QTable, Table or PointingTable

Create pointing\_table attribute.

```
create_all_pointings_wcs(filter_list='white', list_pointings=None, **kwargs)
```

Create all pointing masks one by one as well as the wcs for each individual pointings. Using the grid from the global WCS of the mosaic but restricting it to the range of non-NaN. Hence this needs a global WCS mosaic as a reference to work.

## Input

**filter\_list = list of str**

List of filter names to be used.

**create\_combined\_wcs**(*refcube\_name=None, lambdaminmax\_wcs=[6800, 6805], \*\*kwargs*)

Create the reference WCS from the full mosaic with a given range of lambda.

## Input

**refcube\_name: str**

Name of the cube. Can be None, and then the final datacube from the combine folder will be used.

**wave1: float - optional**

Wavelength taken for the extraction. Should only be present in all spaxels you wish to get.

**prefix\_wcs: str - optional**

Prefix to be added to the name of the input cube. By default, will use "refwcs".

**add\_targetname: bool [True]**

Add the name of the target to the name of the output WCS reference cube. Default is True.

**create\_pointing\_wcs**(*pointing, lambdaminmax\_mosaic=[4700, 9400], filter\_list='white', \*\*kwargs*)

Create the mask of a given pointing And also a WCS file which can then be used to compute individual pointings with a fixed WCS.

## Input

**pointing: int**

Number of the pointing

**lambdaminmax\_mosaic: array of 2 floats**

Default is `lambdaminmax_for_mosaic`, the starting end ending wavelengths needed for a mosaic.

**filter\_list = list of str**

List of filter names to be used.

**Creates:**

pointing mask WCS cube

**returns**

Name of the created WCS cube

**create\_reference\_wcs**(*pointings\_wcs=True, mosaic\_wcs=True, wcs\_refcube\_name=None, refcube\_name=None, folder\_refcube="", list\_pointings=None, \*\*kwargs*)

Create the WCS reference files, for all individual pointings and for the mosaic.

## Input

**pointings\_wcs: bool [True]**

Will run the individual pointings WCS

**mosaic\_wcs: bool [True]**

Will run the combined WCS

**wcs\_refcube\_name: str default=None, optional**

Name of the input WCS to be used. If None (default), we will look at the refcube\_name keyword. If set to 'auto', we will use the default naming conventions to find it on disk. If set to a bona fide name, it will be used as reference WCS.

**refcube\_name: str default=None, optional**

Name of the input cube to guide the WCS building (only used if wcs\_refcube\_name is None). If None, a run\_combine will ensure we have a good reference cube that can be used for the building of a reference WCS. If provided, it will be used as the reference cube to then build the reference WCS.

**folder\_refcube: str, optional**

Folder name for the reference cube or wcs.

**list\_pointings: list of int default=None, optional**

List of pointings to consider

**\*\*kwargs: additional keywords including**

lambdaminmax: [float, float]

**property dict\_pixtabs\_in\_datasets**

**property dict\_pixtabs\_in\_pointings**

**property dict\_tplexpo\_per\_dataset**

**property dict\_tplexpo\_per\_pointing**

**extract\_combined\_narrow\_wcs(name\_cube=None, \*\*kwargs)**

Create the reference WCS from the full mosaic with only 2 lambdas

## Input

**name\_cube: str**

Name of the cube. Can be None, and then the final datacube from the combine folder will be used.

**wave1: float - optional**

Wavelength taken for the extraction. Should only be present in all spaxels you wish to get.

**prefix\_wcs: str - optional**

Prefix to be added to the name of the input cube. By default, will use "refwcs".

**add\_targetname: bool default=True**

Add the name of the target to the name of the output WCS reference cube. Default is True.

**Creates:**

Combined narrow band WCS cube

**returns**

name of the created cube



**filter\_pixables\_with\_list**(*list\_datasets=None, list\_pointings=None*)

Filter a list of pixtables

**Parameters**

- **list\_datasets** (*list of int, optional*) –
- **list\_pointings** (*list of int, optional*) –
- **pointings** (*Filter out the pointing table using those datasets and*) –

**property full\_list\_datasets**

**get\_all\_pixtables**()

List all pixtables in the data folder Fill in the dict\_allpixtabs\_in\_datasets dictionary and creates the pointing table

**get\_pointing\_table**(*\*\*kwargs*)

Create the pointing table from the all pixtables list

Add the pointing\_table attribute and do the selection according to list\_datasets and list\_pointings

**get\_qtable**(*\*\*kwargs*)

Create the qtable from the all pixtables list

**goto\_folder**(*newpath, addtolog=False*)

Changing directory and keeping memory of the old working one

**Input**

**newpath: str**

Nanme of the folder where to go.

**addtolog: bool, optional**

Add this change of folder to the log file.

**goto\_origfolder**(*addtolog=False*)

Go back to original folder

**Input**

**addtolog: bool, optional**

Add this change of folder to the log file.

**goto\_prevfolder**(*addtolog=False*)

Go back to previous folder

## Input

### **addtolog: bool, optional**

Add this change of folder to the log file.

```
run_combine(sof_filename='pointings_combine', lambdaminmax=(4000.0, 10000.0), list_pointings=None,
             suffix='', **kwargs)
```

MUSE Exp\_combine treatment of the reduced pixtables Will run the esorex muse\_exp\_combine routine

### **Parameters**

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **lambdaminmax** (*list of 2 floats*) – Minimum and maximum lambda values to consider for the combine
- **suffix** (*str*) – Suffix to be used for the output name

```
run_combine_all_single_pointings(add_suffix="", sof_filename='pointings_combine',
                                  list_pointings=None, **kwargs)
```

Run for all pointings individually, provided in the list of pointings, by just looping over the pointings.

## Input

### **list\_pointings: list of int**

By default to None (using the default self.list\_pointings). Otherwise a list of pointings you wish to conduct a combine but for each individual pointing.

### **add\_suffix: str**

Additional suffix. 'PXX' where XX is the pointing number will be automatically added to that add\_suffix for each individual pointing.

### **sof\_filename: str**

Name (suffix only) of the sof file for this combine. By default, it is set to 'pointings\_combine'.

### **lambdaminmax: list of 2 floats [in Angstroems]**

Minimum and maximum lambda values to consider for the combine. Default is 4000 and 10000 for the lower and upper limits, resp.

```
run_combine_single_pointing(pointing, add_suffix="", sof_filename='pointing_combine', **kwargs)
```

Running the combine routine on just one single pointing

## Input

### **pointing: int**

Pointing number. No default: must be provided.

### **add\_suffix: str**

Additional suffix. 'PXX' where XX is the pointing number will be automatically added to that add\_suffix.

### **sof\_filename: str**

Name (suffix only) of the sof file for this combine. By default, it is set to 'pointings\_combine'.

**lambdaminmax:** list of 2 floats [in Angstroems]

Minimum and maximum lambda values to consider for the combine. Default is 4000 and 10000 for the lower and upper limits, resp.

**wcs\_from\_pointing:** bool

True by default, meaning that the WCS of the pointings will be used. If not there, will ignore it.

**set\_fullpath\_names()**

Create full path names to be used That includes: root, data, target, but also \_dict\_paths, paths

## pymusepipe.config\_pipe module

MUSE-PHANGS configuration module

`pymusepipe.config_pipe.get_suffix_product(exptype)`

## pymusepipe.create\_sof module

MUSE-PHANGS creating sof file module

**class** `pymusepipe.create_sof.SofDict`

Bases: `OrderedDict`

New Dictionary for the SOF writing Inheriting from ordered Dictionary

**class** `pymusepipe.create_sof.SofPipe`

Bases: `object`

SofPipe class containing all the SOF writing modules

**write\_sof**(*sof\_filename*, *new=False*, *verbose=None*)

Feeding an sof file with input filenames from a dictionary

## pymusepipe.cube\_convolve module

MUSE-PHANGS convolve module

`pymusepipe.cube_convolve.convolution_kernel(input_psf, target_psf, scale=0.2)`

Create the 3D convolution kernel starting from a 3D model of the original PSF and a 2D model of the target PSF using pypher.

### Parameters

*input\_psf* (np.ndarray): 3D array with the model of the original PSF *target\_psf* (np.ndarray): 2D array with a model of the target PSF *scale* (float): spatial scale of both PSF in arcsec/pix

### Returns

**conv\_kernel** (np.ndarray): 3D array with a convolution kernel  
that varies as a function of wavelength.

`pymusepipe.cube_convolve.convolution_kernel_gaussian(fwhm_wave, target_fwhm, target_psf, scale=0.2)`

Create the 3D convolution kernel starting from a 3D model of the original PSF and a 2D model of the target PSF using both gaussian functions.

### Parameters

- **fwHM\_wave** (*array*) – FWHM of the original PSF as a function of wavelength
- **target\_fwhm** (*float*) – fwhm of the target PSF
- **target\_psf** (*np.ndarray*) – target psf2d
- **scale** (*float*) – spatial scale of both PSF in arcsec/pix

**Returns**

**np.ndarray**

3D array with a convolution kernel that varies as a function of wavelength.

**Return type**

conv\_kernel

`pymusepipe.cube_convolve.cube_convolve(data, kernel, variance=None, fft=True, fill_value=nan)`

Convolve a 3D datacube

**Parameters**

- **datacube** –
- **kernel** –

**Returns**

the convolved 3D data and its variance

`pymusepipe.cube_convolve.cube_kernel(shape, wave, input_fwhm, target_fwhm, input_function, target_function, lambda0=6483.58, input_nmoffat=None, target_nmoffat=None, b=-3e-05, scale=0.2, compute_kernel='pypher')`

Main function to create the convolution kernel for the datacube

**Parameters**

- **shape** (*array*) – the shape of the datacube that is going to be convolved. It must be in the form (z, y, x).
- **wave** (*float array*) – wavelengths for the datacube
- **target\_fwhm** (*float*) – fwhm of the target PSF.
- **input\_fwhm** (*float*) – fwhm of the original PSF at the reference wavelength lambda0
- **input\_function** (*str*) – function to be used to describe the input PSF
- **target\_function** (*str*) – function to be used to describe the target PSF
- **lambda0** – float, optional the wavelength at which the original\_fwhm has been measured. Default: 6483.58 (central wavelength of WFI\_BB filter)
- **input\_nmoffat** (*float*) – power index of the original PSF if Moffat [None]
- **target\_nmoffat** (*float*) – power index for the target PSF if Moffat [None]
- **b** (*float*) – steepness of the fwhm vs wavelength relation. Default: -3e-5
- **step** (*float*) – wavelength dispersion in AA/px
- **scale** (*float*) – spatial pixel scale of the PSFs in arcsec/pix
- **compute\_kernel** (*str*) – method to compute the convolution kernel. It can be 'pypher' or 'gaussian'

**Returns**

**np.ndarray**

3D array to be used in the convolution

**Return type**

Kernel

`pymusepipe.cube_convolve.gaussian_kernel(fwhm, size, scale=0.2, **kwargs)`

Gaussian kernel. Input:

**fwhm** (float): fwhm of the Gaussian kernel, in arcsec. **size** (int, ndarray): size of the requested kernel along each axis.

If `size` is a scalar number the final kernel will be a square of side `size`. If `size` has two element they must be in (y\_size, x\_size) order. In each case size must be an integer number of pixels.

**scale** (float): pixel scale of the image **\*\*kwargs**: is there to absorb any additional parameter which could be

provided (but won't be used).

`pymusepipe.cube_convolve.moffat_kernel(fwhm, size, n=1.0, scale=0.2)`

Moffat kernel. Returns a Moffat function array according to given input parameters. Using astropy Moffat2DKernel.

**Parameters**

- **fwhm** (*float*) – fwhm of the Moffat kernel, in arcsec.
- **n** (*float*) – power index of the Moffat
- **size** (*int numpy array*) – size of the requested kernel along each axis. If `size` is a scalar number the final kernel will be a square of side `size`. If `size` has two element they must be in (y\_size, x\_size) order. In each case size must be an integer number of pixels.
- **scale** (*float*) – pixel scale of the image [optional]

`pymusepipe.cube_convolve.psf2d(size, fwhm, function='gaussian', nmoffat=None, scale=0.2)`

Create a model of the target PSF of the convolution. The target PSF does not vary as a function of wavelength, therefore the output is a 2D array.

**Parameters****size: int, array-like**

the size of the final array. If `size` is a scalar number the kernel will be a square of side `size`. If `size` has two elements they must be in (y\_size, x\_size) order.

**fwhm: float**

the FWHM of the psf

**function: str, optional**

the function to model the target PSF. Only 'gaussian' or 'moffat' are accepted. Default: 'gaussian'

**nmoffat** (float): Moffat power index. It must be defined if function = 'moffat'.

Default: None

**scale: float, optional**

the spatial scale of the final kernel

**Returns**

**target: np.ndarray**

a 2D array with the model of the target PSF.

`pymusepipe.cube_convolve.psf3d(wave, size, fwhm0, lambda0=6483.58, b=-3e-05, scale=0.2, nmoffat=None, function='moffat')`

Function to create the cube with the lambda dependent PSF, following a given slope and nominal wavelength.

#### Parameters

**wave: np.ndarray**

array with the wavelength axis of the datacube

**size: int, array-like**

the size of the 2D PSF. If ``size`` is a scalar number the 2D PSF kernel will be a square of side ``size``. If ``size`` has two element they must be in (y\_size, x\_size) order.

**fwhm0: float**

the fwhm at the reference wavelength in arcseconds.

**n: float**

Power index of the Moffat profile. It is usually 2.8 for NOAO cubes and 2.3 for AO cubes.

**lambda0: float**

reference wavelength at which fwhm0 is measured. Default: 6483.58. (It's the average wavelength for the WFI\_BB filter)

**b: float, optional**

the steepness of the relation between wavelength and FWHM. Default: -3e-5 (arcsec/A) (From MUSE team)

**scale: float, optional**

spatial scale of the new datacube in arcsec. Default: 0.2 (MUSE spatial resolution).

function (str): 'moffat' or 'gaussian'

#### Returns

**psf\_cube: np.array**

Datacube containing MUSE PSF as a function of wavelength.

`pymusepipe.cube_convolve.pypher_script(psf_source, psf_target, pixscale_source=0.2, pixscale_target=0.2, angle_source=0.0, angle_target=0.0, reg_fact=0.0001, verbose=False)`

calculate the convolution kernel to move from one PSF to a target one. This is an adaptation of the main pypher script that it is meant to be used from the terminal.

#### Parameters

- **psf\_source** (*ndarray*) – 2D PSF of the source image.
- **psf\_target** (*ndarray*) – target 2D PSF
- **pixscale\_source** (*float*) – pixel scale of the source PSF [0.2]
- **pixscale\_target** (*float*) – pixel scale of the target PSF [0.2]
- **angle\_source** (*float*) – position angle of the source PSF. [0]
- **angle\_target** (*float*) – position angle of the target PSF. [0]
- **reg\_fact** (*float*) – Regularisation parameter for the Wiener filter [1.e-4]
- **verbose** (*bool*) – If True it prints more info on screen [False]

#### Returns

a 2D kernel that convolved with the source PSF

returns the target PSF

### Return type

kernel

## pymusepipe.emission\_lines module

Utility files and functions for wavelengths

`pymusepipe.emission_lines.doppler_shift(wavelength, velocity=0.0)`

Return the redshifted wavelength

`pymusepipe.emission_lines.get_emissionline_band(line='Ha', velocity=0.0, redshift=None, medium='air', lambda_window=10.0)`

Get the wavelengths of an emission line, including a correction for the redshift (or velocity) and a lambda\_window around that line (in Angstroems)

### Parameters

- **line** (name of the line (string)). Default is 'Ha' –
- **velocity** (shift in velocity (km/s)) –
- **medium** ('air' or 'vacuum') –
- **lambda\_window** (lambda\_window in Angstroem) –

`pymusepipe.emission_lines.get_emissionline_wavelength(line='Ha', velocity=0.0, redshift=None, medium='air')`

Get the wavelength of an emission line, including a correction for the redshift (or velocity)

`pymusepipe.emission_lines.print_emission_lines()`

Printing the names of the various emission lines

## pymusepipe.graph\_pipe module

MUSE-PHANGS plotting routines

`class pymusepipe.graph_pipe.GraphMuse(pdf_name='drs_check.pdf', figsize=(10, 14), rect_layout=[0, 0.03, 1, 0.95], verbose=True)`

Bases: `object`

Graphic output to check MUSE data reduction products

`close()`

`plot_page(list_data)`

Plot a set of blocks, each made of a set of spectra or images. This is for 1 page It first counts the number of lines needed according to the separation for images (default is 2 per line, each image taking 2 lines) and spectra (1 spectrum per line over 2 columns)

`plot_set_images(set_of_images=None)`

Plotting a set of images Skipping the ones that are 'None'

`plot_set_spectra(set_of_spectra=None)`

Plotting a set of spectra Skipping the ones that are 'None'

**savepage()**

**start\_page()**

Start the page

`pymusepipe.graph_pipe.open_new_wcs_figure(nfig, mywcs=None)`

Open a new figure (with number `nfig`) with given `wcs`. If not `WCS` is provided, just opens a subplot in that figure.

### Input

**nfig**

[int] Figure number to consider

**mywcs**

[`astropy.wcs.WCS`] Input `WCS` to open a new figure (Default value = `None`)

**returns**

Figure itself with the subplots using the `wcs` projection

**rtype**

fig, subplot

`pymusepipe.graph_pipe.plot_compare_contours(data1, data2, plotwcs=None, labels=('Data1', 'Data2'),  
levels=None, nlevels=10, fignum=1,  
namefig='dummy_contours.png', figfolder="",  
savefig=False, **kwargs)`

Creates a plot with the contours of two input datasets for comparison

### Input

**data1 data2:** 2d `np.array`s

Input arrays to compare

**plotwcs: WCS**

`WCS` used to set the plot if provided

**labels: tuple/list of 2 str**

Labels for the plot

**levels: list of floats**

Levels to be used for the contours. Calculated if `None`.

**fignum: int**

Number for the figure

**namefig: str**

Name of the figure to be saved (if `savefig` is `True`)

**figfolder: str**

Name of the folder for the figure

**savefig: bool**

If `True`, will save the figure as `namefig`



## Creates

Plot with contours of the two input dataset

```
pymusepipe.graph_pipe.plot_compare_cuts(data1, data2, labels=('X', 'Y'), figfolder="", fignum=1,  
                                         namefig='dummy_polypar.png', ncuts=11, savefig=False,  
                                         **kwargs)
```

## Input

data1 data2 label1 label2 figfolder fignum namefig savefig kwargs

## Creates

Plot with a comparison of the two data arrays using regular X and Y cuts

```
pymusepipe.graph_pipe.plot_compare_diff(data1, data2, plotwcs=None, figfolder="", percentage=5,  
                                         fignum=1, namefig='dummy_diff.png', savefig=False,  
                                         **kwargs)
```

### Parameters

- **data1** –
- **data2** –
- **figfolder** –
- **fignum** –
- **namefig** –
- **savefig** –
- **kwargs** –

```
pymusepipe.graph_pipe.plot_polypar(polypar, labels=('Data 1', 'Data 2'), figfolder="", fignum=1,  
                                     namefig='dummy_polypar.png', savefig=False, **kwargs)
```

Creating a plot showing the normalisation arising from a polypar object

### Parameters

- **polypar** –
- **label1** –
- **label2** –
- **foldfig** –
- **namefig** –

```
pymusepipe.graph_pipe.print_fig(text)
```

## pymusepipe.init\_musepipe module

MUSE-PHANGS pipeline wrapper initialisation of folders

```
class pymusepipe.init_musepipe.InitMuseParameters(folder_config='Config/', rc_filename=None,
                                                    cal_filename=None, verbose=True)
```

Bases: `object`

```
init_default_param(dict_param, subattr=None)
```

Initialise the parameters as defined in the input dictionary Hardcoded in config\_pipe.py

### Input

**dict\_param: dict**

Input dictionary defining the attributes

**subattr: str**

Use subattr to add attributes under self.subattr

```
read_param_file(filename, dict_param)
```

Reading an input parameter initialisation file

```
class pymusepipe.init_musepipe.PipeObject(info=None)
```

Bases: `object`

A very simple class used to store astropy tables.

```
pymusepipe.init_musepipe.add_suffix_tokeys(dic, suffix='_folder')
```

## pymusepipe.mpdaf\_pipe module

MUSE-PHANGS mpdaf-functions module

```
class pymusepipe.mpdaf_pipe.BasicFile(filename, **kwargs)
```

Bases: `object`

Basic file with just the name and some properties to attach to that Cube

```
class pymusepipe.mpdaf_pipe.BasicPSF(function='gaussian', fwhm0=0.0, nmoffat=2.8, b=0.0, l0=6483.58,
                                       psf_array=None)
```

Bases: `object`

Basic PSF function and parameters

**property psf\_array**

```
class pymusepipe.mpdaf_pipe.MuseCube(source=None, verbose=False, **kwargs)
```

Bases: `Cube`

Wrapper around the mpdaf Cube functionalities

```
astropy_convolve(other, fft=True, inplace=False)
```

Convolve a DataArray with an array of the same number of dimensions using a specified convolution function.

Copy of `_convolve` for a cube, but doing it per slice or not

Masked values in `self.data` and `self.var` are replaced with zeros before the convolution is performed. However masked pixels in the input data remain masked in the output.

Any variances in `self.var` are propagated correctly.

If `self.var` exists, the variances are propagated using the equation:

```
result.var = self.var (*) other**2
```

where `(*)` indicates convolution. This equation can be derived by applying the usual rules of error-propagation to the discrete convolution equation.

Uses `astropy.convolution.convolve_fft` or `astropy.convolution.convolve`

#### Parameters

- **fft** (*boolean*) – The convolution function to use, chosen from:
  - `astropy.convolution.convolve_fft`
  - `astropy.convolution.convolve`

In general `convolve_fft()` is faster than `convolve()` except when `other.data` only contains a few pixels. However `convolve_fft` uses a lot more memory than `convolve()`, so `convolve()` is sometimes the only reasonable choice. In particular, `convolve_fft` allocates two arrays whose dimensions are the sum of `self.shape` and `other.shape`, rounded up to a power of two. These arrays can be impractically large for some input data-sets.

- **other** (*DataArray or numpy.ndarray*) – The array with which to convolve the contents of `self`. This must have the same number of dimensions as `self`, but it can have fewer elements. When this array contains a symmetric filtering function, the center of the function should be placed at the center of pixel,  $(\text{other.shape} - 1) // 2$ .

Note that passing a `DataArray` object is equivalent to just passing its `DataArray.data` member. If it has any variances, these are ignored.

- **inplace** (*bool*) – If `False` (the default), return a new object containing the convolved array. If `True`, record the convolved array in `self` and return `self`.

#### Return type

`~mpdaf.obj.DataArray`

**build\_filterlist\_images**(*filter\_list, prefix='IMAGE\_FOV', suffix='', folder=None, \*\*kwargs*)

#### Parameters

- **filter\_list** –
- **prefix** –
- **suffix** –
- **folder** –
- **\*\*kwargs** –

Returns:

**convolve\_cube\_to\_psf**(*target\_fwhm, target\_nmoffat=None, target\_function='gaussian', outcube\_folder=None, outcube\_name=None, factor\_fwhm=3, fft=True, erode\_edges=True, npixels\_erosion=2*)

Convolve the cube for a target function 'gaussian' or 'moffat'

#### Parameters

- **target\_fwhm** (*float*) – target FWHM in arcsecond
- **target\_nmoffat** – target n if Moffat function
- **target\_function** (*str*) – ‘gaussian’ or ‘moffat’ [‘gaussian’]
- **factor\_fwhm** (*float*) – number of FWHM for size of Kernel
- **fft** (*bool*) – use FFT to convolve or not [False]
- **perslice** (*bool*) – doing it per slice, or not [True] If doing it per slice, using a direct astropy fft. If doing it with the cube, it uses much more memory but is more efficient as the convolution is done via mpdaf directly.

**Creates:**

Folder and convolved cube names

**create\_reference\_cube**(*lambdamin=4700, lambdamax=9400, step=1.25, outcube\_name=None, filter\_for\_nan=False, \*\*kwargs*)

Create a reference cube using an input one, and overriding the lambda part, to get a new WCS

**Parameters**

- **lambdamin** –
- **lambdamax** –
- **step** –
- **outcube\_name** –
- **filter\_for\_nan** –
- **\*\*kwargs** –

**Returns**

**the name of the folder where**  
the output cube is, and its name

**Return type**

cube\_folder, outcube\_name (*str, str*)

**extract\_onespectral\_cube**(*wave1=6500.0, outcube\_name=None, \*\*kwargs*)

Create a single pixel cube extracted from this one.

**Parameters**

- **wave1** (*float*) – Value of the wavelength to extract. In Angstroms.
- **outcube\_name** (*str*) – Name of the output cube
- **prefix** (*str*) – If outcube\_name is None (default), use that prefix to append in front of the input cube name (same folder)

**Returns**

- *A new cube with only 2 lambda. To be used as a WCS reference for*
- *masks.*

**get\_emissionline\_image**(*line=None, velocity=0.0, redshift=None, lambda\_window=10.0, medium='vacuum'*)

Get a narrow band image around Ha

## Input

lambda\_window: in Angstroems (10 by default). Width of the window of integration medium: vacuum or air (string, 'vacuum' by default) velocity: default is 0. (km/s) redshift: default is None. Overwrite velocity if provided. line: name of the emission line (see emission\_lines dictionary)

**get\_filter\_image**(*filter\_name=None, own\_filter\_file=None, filter\_folder="", dict\_filters=None*)

Get an image given by a filter. If the filter belongs to the filter list, then use that, otherwise use the given file

**get\_image\_from\_cube**(*central\_lambda=None, lambda\_window=0*)

Get image from integrated cube, with spectral pixel centred at central\_lambda and with a lambda\_window of lambda\_window

**get\_quadrant\_spectra\_from\_cube**(*pixel\_window=0*)

Get quadrant spectra from the Cube

## Input

pixel\_window : pixel\_window of integration

**get\_set\_spectra**()

Get a set of standard spectra from the Cube

**get\_spectrum\_from\_cube**(*nx=None, ny=None, pixel\_window=0, title='Spectrum'*)

Get a spectrum from the cube with centre defined in pixels with nx, ny and a window of 'pixel\_window'

**get\_whiteimage\_from\_cube**()

**mask\_trail**(*pq1=[0, 0], pq2=[10, 10], width=1.0, margins=0.0, reset=False, save=True, \*\*kwargs*)

Build a cube mask from 2 points measured from a trail on an image

## Input

**pq1: array or tuple (float)**

p and q coordinates of point 1 along the trail

**pq2: array or tuple (float)**

p and q coordinates of point 2 along the trail

**width: float**

Value (in pixel) of the full slit width to exclude

**margins: float**

Value (in pixel) to extend the slit beyond the 2 extrema If 0, this means limiting it to the extrema themselves. Default is None, which mean infinitely long slit

reset (bool): if True, reset the mask before masking the slit save (bool): if True, save the masked cube

**rebin\_spatial**(*factor, mean=False, inplace=False, full\_covariance=False, \*\*kwargs*)

Combine neighboring pixels to reduce the size of a cube by integer factors along each axis.

Each output pixel is the mean of n pixels, where n is the product of the reduction factors in the factor argument. Uses mpdaf rebin function, but add a normalisation factor if mean=False (sum). It also updates the unit by just copying the old one.

## Input

### factor

[(int or (int,int))] Factor by which the spatial dimensions are reduced

### mean

[bool] If True, taking the mean, if False (default) summing

### inplace

[bool] If False (default) making a copy. Otherwise using the present cube.

### full\_covariance: bool

If True, will assume that spaxels are fully covariant. This means that the variance will be normalised by  $\sqrt{N}$  where  $N$  is the number of summed spaxels. Default is False

### returns

Cube

### rtype

rebinned cube

**save\_mask**(*mask\_name*='dummy\_mask.fits')

Save the mask into a 0-1 image

```
class pymusepipe.mpdaf_pipe.MuseCubeMosaic(ref_wcs, folder_refcube="", folder_cubes="",
                                           prefix_cubes='DATACUBE_FINAL_WCS', list_suffix=[],
                                           use_fixed_cubes=True, excluded_suffix=[],
                                           included_suffix=[], prefix_fixed_cubes='tmask',
                                           verbose=False, pointing_table=None, list_pointings=None,
                                           dict_psf={}, list_cubes=None, **kwargs)
```

Bases: CubeMosaic

**build\_list**(*folder\_cubes*=None, *prefix\_cubes*=None, *list\_cubes*=None, \*\*kwargs)

Building the list of cubes to process

### Parameters

- **folder\_cubes** (*str*) – folder for the cubes
- **prefix\_cubes** (*str*) – prefix to be used

**convolve\_cubes**(*target\_fwhm*, *target\_nmoffat*=None, *target\_function*='gaussian', *suffix*='conv', \*\*kwargs)

### Parameters

- **target\_fwhm** –
- **target\_nmoffat** –
- **input\_function** –
- **target\_function** –
- **suffix** –
- **\*\*kwargs** –

Returns:

property **cube\_names**

**property list\_cubes**

**madcombine**(*folder\_cubes=None, outcube\_name='dummy.fits', fakemode=False, mad=True*)

Combine the CubeMosaic and write it out.

**Parameters**

- **folder\_cubes** (*str*) – name of the folder for the cube [None]
- **outcube\_name** (*str*) – name of the outcube
- **mad** (*bool*) – using mad or not [True]

**Creates:**

A new cube, combination of all input cubes listes in CubeMosaic

**property ncubes****print\_cube\_names()**

**class** pymusepipe.mpdaf\_pipe.**MuseFilter**(*filter\_name='Cousins\_R', filter\_fits\_file='filter\_list.fits', filter\_ascii\_file=None*)

Bases: `object`

**read()**

Reading the data in the file

**class** pymusepipe.mpdaf\_pipe.**MuseImage**(*source=None, \*\*kwargs*)

Bases: `Image`

Wrapper around the mpdaf Image functionalities

**get\_fwhm\_startend()**

Get range of FWHM

**mask\_trail**(*pq1=[0, 0], pq2=[10, 10], width=0.0, reset=False, extent=None*)

Build an image mask from 2 points measured from a trail

**Input****pq1: array or tuple (float)**

p and q coordinates of point 1 along the trail

**pq2: array or tuple (float)**

p and q coordinates of point 2 along the trail

**width: float**

Value (in pixel) of the full slit width to exclude

**extent: float**

Value (in pixel) to extend the slit beyond the 2 extrema If 0, this means limiting it to the extrema themselves. Default is None, which mean infinitely long slit

**reset\_mask()**

Resetting the Image mask

**save\_mask**(*mask\_name='dummy\_mask.fits'*)

Save the mask into a 0-1 image

```
class pymusepipe.mpdaf_pipe.MuseSetImages(*args, **kwargs)
```

Bases: `list`

Set of images

**update**(\*\*kwargs)

```
class pymusepipe.mpdaf_pipe.MuseSetSpectra(*args, **kwargs)
```

Bases: `list`

Set of spectra

**update**(\*\*kwargs)

```
class pymusepipe.mpdaf_pipe.MuseSkyContinuum(filename)
```

Bases: `object`

**integrate**(muse\_filter, ao\_mask=False)

Integrate a sky continuum spectrum using a certain filter file. If the file is a fits file, use it as the MUSE filter list. Otherwise use it as an ascii file

### Input

muse\_filter: MuseFilter

**read**()

Read sky continuum spectrum from MUSE data reduction

**save\_normalised**(norm\_factor=1.0, prefix='norm', overwrite=False)

Normalises a sky continuum spectrum and save it within a new fits file

### Input

**norm\_factor: float**

Scale factor to multiply the input continuum

**prefix: str**

Prefix for the new continuum fits name. Default is 'norm', so that the new file is 'norm\_oldname.fits'

**overwrite: bool**

If True, existing file will be overwritten. Default is False.

**set\_normfactor**(background, filter\_name='Cousins\_R')

Get the normalisation factor given a background value Takes the background value and the sky continuum spectrum and convert this to the scaling Ks needed for this sky continuum The principle relies on having the background measured as:  $MUSE\_calib = ((MUSE - Sky\_cont) + Background) * Norm$

as measured from the alignment procedure.

Since we want:  $MUSE\_calib = ((MUSE - Ks * Sky\_cont) + 0) * Norm$

This means that:  $Ks * Sky\_cont = Sky\_cont - Background ==> Ks = 1 - Background / Sky\_cont$

So we integrate the Sky\_cont to get the corresponding S value and then provide Ks as  $1-B/S$



## Input

**background: float**

Value of the background to consider

**filter\_name: str**

Name of the filter to consider

**class** pymusepipe.mpdaf\_pipe.**MuseSpectrum**(*source=None, \*\*kwargs*)

Bases: `Spectrum`

Wrapper around the mpdaf Spectrum functionalities

**class** pymusepipe.mpdaf\_pipe.**PixTableToMask**(*pixtable\_name, image\_name, suffix\_out='tmask'*)

Bases: `object`

This class is meant to just be a simple tool to mask out some regions from the PixTable using Image masks

**create\_mask**(*pq1=[0, 0], pq2=[10, 10], width=0.0, reset=False, mask\_name='dummy\_mask.fits', extent=None, \*\*kwargs*)

Create the mask and save it in one go

## Input

**pq1: array or tuple (float)**

p and q coordinates of point 1 along the trail

**pq2: array or tuple (float)**

p and q coordinates of point 2 along the trail

**width: float**

Value (in pixel) of the full slit width to exclude

**reset: bool**

By default False, so the mask goes on top of the existing one If True, will reset the mask before building it.

**extent: float**

Value (in pixel) to extend the slit beyond the 2 extrema If 0, this means limiting it to the extrema themselves. Default is None, which mean infinitely long slit

**imshow**(*\*\*kwargs*)

Just showing the image

**mask\_pixtable**(*mask\_name=None, \*\*kwargs*)

Use the Image Mask and create a new Pixtable

## Input

**mask\_name: str**

Name of the mask to be used (FITS file)

**use\_folder: bool**

If True, use the same folder as the Pixtable Otherwise just write where you stand

**suffix\_out: str**

Suffix for the name of the output Pixtable If provided, will overwrite the one in self.suffix\_out

**save\_mask**(*mask\_name='dummy\_mask.fits', use\_folder=True*)

Saving the mask from the Image into a fits file

## Input

**mask\_name: str**

Name of the fits file for the mask

**use\_folder: bool**

If True (default) will look for the mask in the image\_folder. If False, will just look for it where the command is run.

## Creates

A fits file with the mask as 0 and 1

`pymusepipe.mpdaf_pipe.get_sky_spectrum(specname)`

Read sky spectrum from MUSE data reduction

`pymusepipe.mpdaf_pipe.integrate_spectrum(spectrum, wave_filter, throughput_filter, ao_mask=False)`

Integrate a spectrum using a certain Muse Filter file.

## Input

**spectrum: Spectrum**

Input spectrum given as an mpdaf Spectrum

**wave\_filter: float array**

Array of wavelength for the filter

**throughput\_filter: float array**

Array of throughput (between 0 and 1) for the filter. Should be the same dimension (1D, N floats) as wave\_filter

`pymusepipe.mpdaf_pipe.rotate_cube_wcs(cube_name, cube_folder='', outwcs_folder=None, rotangle=0.0, **kwargs)`

Routine to remove potential Nan around an image and reconstruct an optimal WCS reference image. The rotation angle is provided as a way to optimise the extent of the output image, removing Nan along X and Y at that angle.

## Parameters

- **cube\_name** (*str*) – input image name. No default.
- **cube\_folder** (*str*) – input image folder [‘’]

- **outwcs\_folder** (*str*) – folder where to write the output frame. Default is None which means that it will use the folder of the input image.
- **rotangle** (*float*) – rotation angle in degrees [0]
- **\*\*kwargs** – in\_suffix (*str*): in suffix to remove from name ['prealign'] out\_suffix (*str*): out suffix to add to name ['rotwcs'] margin\_factor (*float*): factor to extend the image [1.1]

Returns:

```
pymusepipe.mpdaf_pipe.rotate_image_wcs(ima_name, ima_folder='', outwcs_folder=None, rotangle=0.0,
                                         **kwargs)
```

Routine to remove potential Nan around an image and reconstruct an optimal WCS reference image. The rotation angle is provided as a way to optimise the extent of the output image, removing Nan along X and Y at that angle.

## Input

**ima\_name: str**

input image name. No default.

**ima\_folder: str default='', optional**

input image folder

**outwcs\_folder: str, optional**

folder where to write the output frame. Default is None which means that it will use the folder of the input image.

**rotangle: float default=0, optional**

rotation angle in degrees

**in\_suffix: str default='prealign'**

in suffix to remove from name

**out\_suffix: str default='rotwcs'**

out suffix to add to name

**margin\_factor: float**

factor to extend the image [1.1]

## pymusepipe.musepipe module

MUSE-PHANGS core module. This defines the main class (MusePipe) which can be used throughout this package.

This module is a complete rewrite of a pipeline wrapper for the MUSE dataset. All classes and objects were refactored.

However, the starting point of this package has been initially inspired by several pieces of python codes developed by various individuals, including Kyriakos and Martina from the GTO MUSE MAD team and further rewritten by Mark van den Brok. Hence: a big Thanks to all three for this!

Note that several python packages exist which would provide similar (or better) functionalities.

Eric Emsellem adapted a version from early 2017, provided by Mark and adapted it for the needs of the PHANGS project (PI Schinnerer). It was further refactored starting from scratch but keeping a few initial ideas.

```
class pymusepipe.musepipe.MusePipe(targetname=None, dataset=1, folder_config='Config',
                                    rc_filename=None, cal_filename=None, log_filename='MusePipe.log',
                                    verbose=True, musemode='WFM-NOAO-N', checkmode=True,
                                    strong_checkmode=False, **kwargs)
```

Bases: *PipePrep*, *PipeRecipes*

Main Class to define and run the MUSE pipeline, given a certain galaxy name. This is the main class used throughout the running of the pipeline which contains functions and attributes all associated with the reduction of MUSE exposures.

It inherits from the PipePrep class, which prepares the recipes for the running of the MUSE pipeline, and Piperecipes which has the recipes described.

**goto\_folder**(*newpath*, *addtolog=False*)

Changing directory and keeping memory of the old working one

**Parameters**

- **newpath** (*str*) – Path where to go to
- **addtolog** (*bool* [*False*]) – Adding the folder move to the log file

**goto\_origfolder**(*addtolog=False*)

Go back to original folder

**goto\_prevfolder**(*addtolog=False*)

Go back to previous folder

**Parameters**

- **addtolog** (*bool* [*False*]) – Adding the folder move to the log file

**init\_raw\_table**(*reset=False*, *\*\*kwargs*)

Create a fits table with all the information from the Raw files. Also create an astropy table with the same info

**Parameters**

- **reset** (*bool* [*False*]) – Resetting the raw astropy table if True

**property musemode**

Mode for MUSE

**print\_musemodes**()

Print out the list of allowed muse modes

**read\_all\_astro\_tables**(*reset=False*)

Initialise all existing Astropy Tables

**read\_astropy\_table**(*expotype=None*, *stage='master'*)

Read an existing Masterfile data table to start the pipeline

**retrieve\_geoastro\_name**(*date\_str*, *filetype='geo'*, *fieldmode='wfm'*)

Retrieving the astrometry or geometry fits file name

**Parameters**

- **date\_str** (*str*) – Date as a string (DD/MM/YYYY)
- **filetype** (*str*) – 'geo' or 'astro', type of the needed file
- **fieldmode** (*str*) – 'wfm' or 'nfm' - MUSE mode

**save\_expo\_table**(*expotype*, *tpl\_gtable*, *stage='master'*, *fits\_tablename=None*, *aggregate=True*, *suffix=""*, *overwrite=None*, *update=None*)

Save the Expo (Master or not) Table corresponding to the expotype

**set\_fullpath\_names()**

Create full path names to be used

**sort\_raw\_tables**(*checkmode=None, strong\_checkmode=None*)

Provide lists of exposures with types defined in the dictionary after excluding those with the wrong MUSE mode if checkmode is set up.

**Input****checkmode: boolean**

Checking the MUSE mode or not. Default to None, namely it won't use the value set here but the value predefined in self.checkmode.

**strong\_checkmode: boolean**

Strong check, namely in case you still wish to force the MUSE mode even for files which are not mode specific (e.g., BIAS). Default to None, namely it uses the self.strong\_checkmode which was already set up at start.

**pymusepipe.prep\_recipes\_pipe module**

MUSE-PHANGS preparation recipe module

**class** pymusepipe.prep\_recipes\_pipe.**PipePrep**(*first\_recipe=1, last\_recipe=None*)

Bases: [SofPipe](#)

PipePrep class prepare the SOF files and launch the recipes

**get\_align\_group**(*name\_ima\_reference=None, list\_expo=[], line=None, suffix="", bygroup=False, \*\*kwargs*)

Extract the needed information for a set of exposures to be aligned

**static print\_recipes()**

Printing the list of recipes

**run\_align\_bydataset**(*sof\_filename='exp\_align\_bydataset', expotype='OBJECT', list\_expo=[], stage='processed', line=None, suffix="", tpl='ALL', \*\*kwargs*)

Aligning the individual exposures from a dataset using the emission line region With the muse exp\_align routine

**Parameters**

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_align\_bygroup**(*sof\_filename='exp\_align\_bygroup', expotype='OBJECT', list\_expo=[], stage='processed', line=None, suffix="", tpl='ALL', \*\*kwargs*)

Aligning the individual exposures from a dataset using the emission line region With the muse exp\_align routine

**Parameters**

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_autocal\_sky**(*sof\_filename*='scipost', *expotype*='SKY', *AC\_suffix*='\_AC', *tpl*='ALL', *\*\*extra\_kwargs*)

Launch the scipost command to get individual exposures in a narrow band filter

**run\_bias**(*sof\_filename*='bias', *tpl*='ALL', *update*=None)

Reducing the Bias files and creating a Master Bias Will run the esorex muse\_bias command on all Biases

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_check\_align**(*name\_offset\_table*, *sof\_filename*='scipost', *expotype*='OBJECT', *tpl*='ALL', *line*=None, *suffix*='', *folder\_offset\_table*=None, *\*\*extra\_kwargs*)

Launch the scipost command to get individual exposures in a narrow band filter to check if the alignments are ok (after rotation and using a given offset\_table)

**run\_combine\_dataset**(*sof\_filename*='exp\_combine', *expotype*='OBJECT', *list\_expo*=[], *stage*='processed', *tpl*='ALL', *lambdaminmax*=[4000.0, 10000.0], *suffix*='', *\*\*kwargs*)

Produce a cube from all frames in the dataset list\_expo or tpl specific arguments can still reduce the selection if needed

**run\_fine\_alignment**(*name\_ima\_reference*=None, *nexpo*=1, *list\_expo*=[], *line*=None, *bygroup*=False, *reset*=False, *\*\*kwargs*)

Run the alignment on this dataset using or not a reference image

**run\_flat**(*sof\_filename*='flat', *tpl*='ALL', *update*=None)

Reducing the Flat files and creating a Master Flat Will run the esorex muse\_flat command on all Flats

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_lsf**(*sof\_filename*='lsf', *tpl*='ALL', *update*=None)

Reducing the LSF files and creating the LSF PROFILE Will run the esorex muse\_lsf command on all Flats

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_phangs\_recipes**(*fraction*=0.8, *illum*=True, *skymethod*='model', *\*\*kwargs*)

Running all PHANGS recipes in one shot Using the basic set up for the general list of recipes

## Input

### **fraction: float**

Fraction of sky to consider in sky frames for the sky spectrum Default is 0.8.

### **illum: bool**

Default is True (use illumination during twilight calibration)

### **skymethod: str**

Default is “model”.

**run\_prep\_align**(sof\_filename='scipost', expotype='OBJECT', tpl='ALL', line=None, suffix='',  
\*\*extra\_kwargs)

Launch the scipost command to get individual exposures in a narrow band filter

**run\_recipes**(\*\*kwargs)

Running all recipes in one shot

## Input

### **fraction: float**

Fraction of sky to consider in sky frames for the sky spectrum Default is 0.8.

### **illum: bool**

Default is True (use illumination during twilight calibration)

### **skymethod: str**

Default is “model”.

### **filter\_for\_alignment: str**

Default is defined in config\_pipe

### **line: str**

Default is None as defined in config\_pipe

### **lambda\_window: float**

Default is 10.0 as defined in config\_pipe

**run\_scibasic**(sof\_filename='scibasic', expotype='OBJECT', tpl='ALL', illum=True, update=True,  
overwrite=True)

Reducing the files of a certain category and creating the PIXTABLES Will run the esorex muse\_scibasic

### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_scibasic\_all**(list\_object=['OBJECT', 'SKY', 'STD'], tpl='ALL', illum=True, \*\*kwargs)

Running scibasic for all objects in list\_object Making different sof for each category

**run\_scipost**(sof\_filename='scipost', expotype='OBJECT', tpl='ALL', stage='processed', list\_expo=[],  
lambdaminmax=[4000.0, 10000.0], suffix='', \*\*kwargs)

Scipost treatment of the objects Will run the esorex muse\_scipost routine

## Input

**sof\_filename:** string (without the file extension)

Name of the SOF file which will contain the Bias frames

**tpl:** ALL by default or a special tpl time list\_expo: list of integers

Exposure numbers. By default, an empty list which means that all exposures will be used.

**lambdaminmax:** tuple of 2 floats

Minimum and Maximum wavelength to pass to the muse\_scipost recipe

**suffix:** str

Suffix to add to the input pixtables.

**norm\_skycontinuum:** bool

Normalise the skycontinuum or not. Default is False. If normalisation is to be done, it will use the offset\_table and the tabulated background value to renormalise the sky continuum.

**skymethod:** str

Type of skymethod. See MUSE manual.

**offset\_list:** bool

If True, using an OFFSET list. Default is True.

**name\_offset\_table:** str

Name of the offset table table. If not provided, will use the default name produced during the pipeline run.

**filter\_for\_alignment:** str

Name of the filter used for alignment. Default is self.filter\_for\_alignment

**filter\_list:** str

List of filters to be considered for reconstructed images. By Default will use the list in self.filter\_list.

**run\_scipost\_perexpo**(sof\_filename='scipost', expotype='OBJECT', list\_tplexpo='ALL', stage='processed', suffix='', offset\_list=False, \*\*kwargs)

Launch the scipost command exposure per exposure

## Input

See run\_scipost parameters

**run\_scipost\_sky()**

Run scipost for the SKY with no offset list and no skymethod

**run\_sky**(sof\_filename='sky', tpl='ALL', fraction=0.8, update=None, overwrite=True)

Reducing the SKY after they have been scibasic reduced Will run the esorex muse\_create\_sky routine

### Parameters

- **sof\_filename** (string (without the file extension)) – Name of the SOF file which will contain the Bias frames
- **tpl** (ALL by default or a special tpl time) –



**run\_standard**(*sof\_filename*='standard', *tpl*='ALL', *update*=None, *overwrite*=True)

Reducing the STD files after they have been obtained Running the muse\_standard routine

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_twilight**(*sof\_filename*='twilight', *tpl*='ALL', *update*=None, *illum*=True)

Reducing the files and creating the TWILIGHT CUBE. Will run the esorex muse\_twilight command on all TWILIGHT

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**run\_wave**(*sof\_filename*='wave', *tpl*='ALL', *update*=None)

Reducing the WAVE-CAL files and creating the Master Wave Will run the esorex muse\_wave command on all Flats

#### Parameters

- **sof\_filename** (*string (without the file extension)*) – Name of the SOF file which will contain the Bias frames
- **tpl** (*ALL by default or a special tpl time*) –

**save\_fine\_alignment**(*name\_offset\_table*=None)

Save the fine dataset alignment

**select\_tpl\_files**(*expotype*=None, *tpl*='ALL', *stage*='raw')

Selecting a subset of files from a certain type

`pymusepipe.prep_recipes_pipe.add_listpath(suffix, paths)`

Add a suffix to a list of path and normalise them

`pymusepipe.prep_recipes_pipe.norm_listpath(paths)`

Normalise the path for a list of paths

`pymusepipe.prep_recipes_pipe.print_my_function_name(f)`

Function to provide a print of the name of the function Can be used as a decorator

## pymusepipe.recipes\_pipe module

MUSE-PHANGS recipe module

```
class pymusepipe.recipes_pipe.PipeRecipes(nifu=-1, first_cpu=0, ncpu=24, list_cpu=[],
                                           likwid='likwid-pin -c N:', fakemode=False, domerge=True,
                                           nocache=False, nochecksum=True)
```

Bases: `object`

PipeRecipes class containing all the esorex recipes for MUSE data reduction

**property checksum**

**property esorex**

**joinprod**(*name*)

**property merge**

**recipe\_align**(*sof, dir\_products, namein\_products, nameout\_products, tpl, group, threshold=10.0, srcmin=3, srcmax=80, fwhm=5.0*)

Running the muse\_exp\_align recipe

**recipe\_bias**(*sof, dir\_bias, name\_bias, tpl*)

Running the esorex muse\_bias recipe

**recipe\_combine**(*sof, dir\_products, name\_products, tpl, expotype, suffix\_products="", suffix\_prefinalnames="", prefix\_products="", save='cube', pixfrac=0.6, suffix="", format\_out='Cube', filter\_list='white', lambdamin=4000.0, lambdamax=10000.0*)

Running the muse\_exp\_combine recipe for one single dataset

**recipe\_combine\_pointings**(*sof, dir\_products, name\_products, suffix\_products="", suffix\_prefinalnames="", prefix\_products="", save='cube', pixfrac=0.6, suffix="", format\_out='Cube', filter\_list='white', lambdamin=4000.0, lambdamax=10000.0*)

Running the muse\_exp\_combine recipe for pointings

**recipe\_flat**(*sof, dir\_flat, name\_flat, dir\_trace, name\_trace, tpl*)

Running the esorex muse\_flat recipe

**recipe\_lsf**(*sof, dir\_lsf, name\_lsf, tpl*)

Running the esorex muse\_lsf recipe

**recipe\_scibasic**(*sof, tpl, expotype, dir\_products=None, name\_products=[], suffix=""*)

Running the esorex muse\_scibasic recipe

**recipe\_scipost**(*sof, tpl, expotype, dir\_products="", name\_products=[""], suffix\_products=[""], suffix\_prefinalnames=[""], suffix\_postfinalnames=[""], list\_expo=[], save='cube,skymodel', filter\_list='white', skymethod='model', pixfrac=0.8, darcheck='none', skymodel\_frac=0.05, astrometry='TRUE', lambdamin=4000.0, lambdamax=10000.0, suffix="", autocalib='none', rvcorr='bary', \*\*kwargs*)

Running the esorex muse\_scipost recipe

**recipe\_sky**(*sof, dir\_sky, name\_sky, tpl, iexpo=1, fraction=0.8*)

Running the esorex muse\_stc recipe

**recipe\_std**(*sof, dir\_std, name\_std, tpl*)

Running the esorex muse\_stc recipe

**recipe\_twilight**(*sof, dir\_twilight, name\_twilight, tpl*)

Running the esorex muse\_twilight recipe

**recipe\_wave**(*sof, dir\_wave, name\_wave, tpl*)

Running the esorex muse\_wavecal recipe

**run\_oscommand**(*command, log=True*)

Running an os.system shell command Fake mode will just spit out the command but not actually do it.

**write\_errlogfile**(*text*)

Writing in log file

**write\_logfile**(*text*, *addext=""*)

Writing in log file

**write\_outlogfile**(*text*)

Writing in log file

## pymusepipe.target\_sample module

MUSE-PHANGS target sample module

**class** pymusepipe.target\_sample.**MusePipeSample**(*TargetDic*, *rc\_filename=None*, *cal\_filename=None*, *folder\_config=""*, *first\_recipe=1*, *\*\*kwargs*)

Bases: `object`

**combine\_target**(*targetname=None*, *\*\*kwargs*)

Run the combine recipe. Shortcut for `combine[targetname].run_combine()`

**combine\_target\_per\_pointing**(*targetname=None*, *wcs\_from\_pointing=True*, *\*\*kwargs*)

Run the combine recipe. Shortcut for `combine[targetname].run_combine()`

**convolve\_mosaic\_per\_pointing**(*targetname=None*, *list\_pointings=None*, *dict\_psf={}*, *target\_fwhm=0.0*, *target\_nmoffat=None*, *target\_function='gaussian'*, *suffix=None*, *best\_psf=True*, *min\_dfwhm=0.2*, *fakemode=False*, *\*\*kwargs*)

Convolve the datacubes listed in a mosaic with some target function and FWHM. It will try to homogeneise all individual cubes to that target PSF.

### Parameters

- **targetname** (*str*) – name of the target
- **list\_pointings** (*list*) – list of pointing numbers for the list of pointings to consider
- **dict\_psf** (*dict*) – dictionary providing individual PSFs per pointing
- **target\_fwhm** (*float*) – target FWHM for the convolution [arcsec]
- **target\_nmoffat** (*float*) – tail factor for the moffat function.
- **target\_function** (*str*) – ‘moffat’ or ‘gaussian’ [‘gaussian’]
- **suffix** (*str*) – input string to be added
- **best\_psf** (*bool*) – if True use the minimum overall possible value. If True it will overwrite all the target parameters.
- **min\_dfwhm** (*float*) – minimum difference to be added in quadrature [in arcsec]
- **filter\_list** (*list*) – list of filters to be used for reconstructing images
- **fakemode** (*bool*) – if True, will only initialise parameters but not proceed with the convolution.
- **\*\*kwargs** –

Returns:

**create\_reference\_wcs**(*targetname=None*, *pointings\_wcs=True*, *mosaic\_wcs=True*, *wcs\_refcube\_name=None*, *refcube\_name=None*, *\*\*kwargs*)

Run the combine for individual exposures first building up a mask.

```
finalise_reduction(targetname=None, rot_pixtab=False, create_wcs=True, create_expocubes=True,  
                    create_pixtables=True, create_pointingcubes=True, name_offset_table=None,  
                    folder_offset_table=None, list_datasets=None, **kwargs)
```

Finalise the reduction steps by using the offset table, rotating the pixeltables, then reconstructing the PIXTABLE\_REDUCED, produce reference WCS for each pointing, and then run the reconstruction of the final individual cubes

#### Parameters

- **targetname** (*str*) –
- **rot\_pixtab** (*bool*) –
- **create\_wcs** (*bool*) –
- **create\_expocubes** (*bool*) –
- **name\_offset\_table** (*str*) –
- **folder\_offset\_table** (*str*) –
- **\*\*kwargs** – include wcs\_refcube\_name: str  
Reference WCS (cube) to be used to project all cubes

**refcube\_name: str**

Reference cube which will be use to build a reference WCS

**folder\_refcube: str**

Name of the folder where to find the reference WCS or cube

Returns:

```
init_combine(targetname=None, list_pointings=None, list_datasets=None, folder_offset_table=None,  
              name_offset_table=None, **kwargs)
```

Prepare the combination of targets. The use can provide a pointing table providing a given selection.

#### Input

**targetname: str [None]**

Name of target

**list\_pointings: list [or None=default= all pointings]**

List of pointings (e.g., [1,2,3])

**name\_offset\_table: str**

Name of Offset table

**\*\*kwargs: additional keywords including**

pointing\_table, pointing\_table\_folder, pointing\_table\_format

```
init_mosaic(targetname=None, list_datasets=None, list_pointings=None, pointing_table=None, **kwargs)
```

Prepare the combination of targets

## Input

**targetname: str [None]**

Name of target

**list\_datasets: list [or None=default meaning all datasets]**

List of datasets (e.g., [1,2,3])

**pointing\_table: PointingTable**

Pointing Table to select a given set of exposures

**mosaic**(*targetname=None, list\_pointings=None, init\_mosaic=True, build\_cube=True, build\_images=True, \*\*kwargs*)

### Parameters

- **targetname** –
- **list\_pointings** –
- **\*\*kwargs** –

Returns:

**reduce\_all\_targets**(*\*\*kwargs*)

Reduce all targets already initialised

## Input

**first\_recipe: int or str**

One of the recipe to start with

**last\_recipe: int or str**

One of the recipe to end with

**reduce\_target**(*targetname=None, list\_datasets=None, \*\*kwargs*)

Reduce one target for a list of datasets

## Input

**targetname: str**

Name of the target

**list\_datasets: list**

Dataset numbers. Default is None (meaning all datasets indicated in the dictionary will be reduced)

**first\_recipe: str or int [1]** **last\_recipe: str or int [max of all recipes]**

Name or number of the first and last recipes to process

**reduce\_target\_postalign**(*targetname=None, list\_datasets=None, \*\*kwargs*)

Reduce target for all steps after pre-alignment

## Input

**targetname: str**

Name of the target

**list\_datasets: list**

Dataset numbers. Default is None (meaning all datasets indicated in the dictionary will be reduced)

**reduce\_target\_prealign**(*targetname=None, list\_datasets=None, \*\*kwargs*)

Reduce target for all steps before pre-alignment (included)

## Input

**targetname: str**

Name of the target

**list\_datasets: list**

Dataset numbers. Default is None (meaning all datasets indicated in the dictionary will be reduced)

**rotate\_pixtables\_target**(*targetname=None, list\_datasets=None, folder\_offset\_table=None, name\_offset\_table=None, fakemode=False, \*\*kwargs*)

Rotate all pixel table of a certain targetname and datasets

**run\_target\_recipe**(*recipe\_name, targetname=None, list\_datasets=None, \*\*kwargs*)

Run just one recipe on target

## Input

**recipe\_name: str targetname: str**

Name of the target

**list\_datasets: list**

Pointing numbers. Default is None (meaning all datasets indicated in the dictionary will be reduced)

**run\_target\_scipost\_perexpo**(*targetname=None, list\_datasets=None, list\_pointings=None, folder\_offset\_table=None, name\_offset\_table=None, \*\*kwargs*)

Build the cube per exposure using a given WCS

### Parameters

- **targetname** –
- **list\_datasets** –
- **\*\*kwargs** –

Returns:

**set\_pipe\_target**(*targetname=None, list\_datasets=None, \*\*kwargs*)

Create the musepipe instance for that target and list of datasets

## Input

**targetname: str**

Name of the target

**list\_datasets: list**

Dataset numbers. Default is None (meaning all datasets indicated in the dictionary will be reduced)

**config\_args: dic**

Dictionary including extra configuration parameters to pass to MusePipe. This allows to define a global configuration. If self.\_\_phangs is set to True, this is overwritten with the default PHANGS configuration parameters as provided in config\_pipe.py.

```
class pymusepipe.target_sample.MusePipeTarget(targetname="", subfolder='P100', list_datasets=None)
```

Bases: `object`

```
class pymusepipe.target_sample.PipeDict(*args, **kwargs)
```

Bases: `dict`

Dictionary with extra attributes

**run\_on\_all\_keys(funcname)**

Runs the given function on all the keys

**setdefault(key, value=None)**

Insert key with a value of default if key is not in the dictionary.

Return the value for key if key is in the dictionary, else default.

**update([E], \*\*F) → None.** Update D from dict/iterable E and F.

If E is present and has a .keys() method, then does: for k in E: D[k] = E[k] If E is present and lacks a .keys() method, then does: for k, v in E: D[k] = v In either case, this is followed by: for k in F: D[k] = F[k]

```
pymusepipe.target_sample.insert_suffix(filename, suffix="")
```

Create a new filename including the suffix in the name

## Input

filename: str suffix: str

```
pymusepipe.target_sample.update_calib_file(filename, subfolder="", folder_config="")
```

Update the rcfile with a new root

## Input

**filename: str**

Name of the input filename

**folder\_config: str**

Default is "". Name of folder for filename

**subfolder: str**

Name of subfolder to add in the path

## pymusepipe.util\_image module

Utility functions for images in pymusepipe

**class** pymusepipe.util\_image.CircleZone

Bases: [SelectionZone](#)

Define a Circular zone, defined by a center and a radius

**select**(*xin*, *yin*)

Define a selection within a circle

### Input

**xin, yin: 2d arrays**

Input positions for the spaxels

**class** pymusepipe.util\_image.PointingTable(*input\_table=None*, *\*\*kwargs*)

Bases: [object](#)

**assign\_pointings**(*\*\*kwargs*)

Assign pointing according to distance rules. Will also update the centre values.

**\*\*kwargs: additional keywords including**

verbose: bool default=self.verbose overwrite: bool default=False

overwrite the pointing

### Updates

The values of the 'pointing' column for the selected filenames ('select'==1)

**property dict\_allnames\_in\_datasets**

Dictionary of the names per dataset

**property dict\_allnames\_in\_pointings**

Dictionary of the names per pointing

**property dict\_names\_in\_datasets**

Dictionary of the names per dataset

**property dict\_names\_in\_pointings**

Dictionary of the names per pointing

**property dict\_tplexpo\_per\_dataset**

**property dict\_tplexpo\_per\_pointing**

**property fullnameout**

**property fulltablename**

**list\_colnames\_ptable** = ['filename', 'dataset', 'tpls', 'expo']

**property list\_datasets**

List of unique datasets in the pointing table



**property list\_pointings**

List of unique pointings in the pointing table

**read(\*\*kwargs)**

Read the input filename in given folder assuming a given format.

**Input****filename: str, optional**

Name of the filename

**folder: str default="", optional**

Name of the folder where to find the filename

table\_format: str default='ascii'

**rtype**

self.qtable with the content of the file

**scan\_folder(folder=None, \*\*kwargs)**

Scan a folder to create a full pointing table

**Input****folder: str default to None**

If not provided, will use the default self.folder

**\*\*kwargs:**

Other keywords are passed to create\_pointing\_table\_from\_folder

**Creates**

Attribute qtable

**select\_datasets(\*\*kwargs)**

Select all filenames with a given list of datasets

**Input**

list\_datasets: list of int, optional

**Updates**

'select' values in the astropy pointing table according to the list of datasets

**select\_filename(filename, verbose=False)**

Select the filename as provided, by putting the value of column 'select' to 1

## Input

### **filename: str**

Name of the file (see column 'filename')

Put the right value of the 'select' column to 1

### **select\_pointings(\*\*kwargs)**

Select all filenames with pointings in the pointing list

## Input

list\_pointings: list of int, optional

## Updates

'select' values in the astropy pointing table according to the list of pointings

### **select\_pointings\_and\_datasets(\*\*kwargs)**

Select all filenames with that pointing or dataset number.

## Input

list\_pointings: list of int, optional list\_datasets: list of int, optional

## Updates

'select' values in the astropy pointing table according to the list of pointings and datasets

### **property selected\_filenames**

Return the list of filenames following the selection

#### **Return type**

list\_filename

### **set\_select\_value(filename, value=1, verbose=False)**

Set the value of the select column to 1, according to a given filename

filename: str value: int default 1

### **unselect\_filename(filename, verbose=False)**

Select the filename as provided, by putting the value of column 'select' to 1

## Input

### **filename: str**

Name of the file (see column 'filename')

Put the right value of the 'select' column to 1

**write**(*overwrite=False, \*\*kwargs*)

Write out the table on disk, using the nameout and provided folder.

### **Parameters**

- **overwrite** (*bool default=False*) –
- **\*\*kwargs** – Valid keywords are folder: str nameout: str Extra keywords are passed to the astropy QTable.write() function
- **disk** (*Writes the pointing table on*) –

**class** pymusepipe.util\_image.**RectangleZone**

Bases: [SelectionZone](#)

Define a rectangular zone, given by a center, a length, a width and an angle

**select**(*xin, yin*)

### **Define a selection within a rectangle**

It can be rotated by an angle theta (in degrees)

## Input

### **xin, yin: 2d arrays**

Input positions for the spaxels

**class** pymusepipe.util\_image.**SelectionZone**(*params=None*)

Bases: [object](#)

Parent class for Rectangle\_Zone and Circle\_Zone

## Input

### **params: list of floats**

List of parameters for the selection zone

**class** pymusepipe.util\_image.**TrailZone**

Bases: [SelectionZone](#)

Define a Trail zone, defined by two points and a width

**select**(*xin, yin*)

Define a selection within trail

## Input

**xin, yin: 2d arrays**

Input positions for the spaxels

`pymusepipe.util_image.check_column_set(input_table)`

Check the minimum column set for the Pointing table

## Input

input\_table: astropy Table

**returns**

**bool**

**rtype**

True if all names are in the table, False otherwise

`pymusepipe.util_image.chunk_stats(list_arrays, chunk_size=15)`

Cut the datasets in 2d chunks and take the median Return the set of medians for all chunks.

### Parameters

- **list\_arrays** (*list of np.arrays*) – List of arrays with the same sizes/shapes
- **chunk\_size** (*int*) – number of pixel (one D of a 2D chunk) of the chunk to consider (Default value = 15)

### Returns

**median, standard** – for the given datasets analysed in chunks.

### Return type

2 arrays of the medians and standard deviations

`pymusepipe.util_image.compute_diagnostics(pointing_dict, center_dict)`

Compute the average and std of the distance between the exposures belonging to the same pointing.

## Input

**pointing\_dict: dict**

Dictionary for the pointings

**center\_dict: dict**

dictionary of the files to be used

**returns**

**Diagnostic** – Each pointing key has its [mean, std] as value of the distionary

**rtype**

dict

`pymusepipe.util_image.create_offset_table(image_names, table_folder="",  
table_name='dummy_offset_table.fits', overwrite=False)`

Create an offset list table from a given set of images. It will use the MJD and DATE as read from the descriptors of the images. The names for these keywords is stored in the dictionary default\_offset\_table from config\_pipe.py

### Parameters

- **image\_names** (*list of str*) – List of image names to be considered. (Default value = [])
- **table\_folder** (*str*) – folder of the table (Default value = “”)
- **table\_name** (*str*) – name of the table to save [‘dummy\_offset\_table.fits’] (Default value = “dummy\_offset\_table.fits”)
- **overwrite** (*bool*) – if the table exists, it will be overwritten if set to True only. (Default value = False)
- **overwrite** – if the table exists, it will be overwritten if set to True only. (Default value = False)

**Return type**

A fits table with the output given name. (Default value = False)

`pymusepipe.util_image.crop_data(data, border=10)`

Crop a 2D data and return it cropped after a border has been removed (number of pixels) from each edge (borderx2 pixels are removed from each dimension)

**Input****data: 2d array**

Array which has the signal to be cropped

**border: int**

Number of pixels to be cropped at each edge

**returns**

**cdata** – Cropped data array

**rtype**

2d array

`pymusepipe.util_image.filter_list_with_pointingtable(input_list, pointing_table=None, verbose=True, str_dataset='OB', ndigits=3, list_pointings=None, filtername=None)`

**Input****input\_list: list of str**

Input list of filenames to filter

pointing\_table: PointingTable or QTable or Table str\_dataset: str default=default\_str\_dataset ndigits: int default=default\_ndigits filtername: str default=None verbose: bool default=True

`pymusepipe.util_image.filtermed_image(data, border=0, filter_size=2, keepnan=False)`

Process image by removing the borders and filtering it via a median filter

## Input

**data: 2d array**

Array to be processed

**border: int**

Number of pixels to remove at each edge

**filter\_size: float**

Size of the filtering (median)

**returns**

**cdata** – Processed array

**rtype**

2d array

```
pymusepipe.util_image.flatclean_image(data, border=10, dynamic_range=10, median_window=10,  
                                       threshold=0.0, squeeze=True, remove_bkg=True)
```

Process image by squeezing the range, removing the borders and filtering it. The image is first filtered, then it is cropped. All values below a given minimum are set to 0 and all Nan set to 0 or infinity accordingly.

## Input

**data: 2d ndarray**

Input array to process

**dynamic\_range: float [10]**

Dynamic range used to squash the bright pixels down

**median\_window: int [10]**

Size of the window used for the median filtering.

**threshold: float [0]**

Value of the minimum value allowed.

**squeeze: bool**

Squeeze the dynamic range by using the dynamic\_range variable

**crop: bool**

Crop the borders using border as the variable

remove\_bkg: remove the filter\_mediated background

**returns**

**flatcleaned\_array**

**rtype**

2d ndarray

```
pymusepipe.util_image.get_centre_from_image_or_cube(filename, ext=1, dtype='image')
```

Compute the coordinate of the center of the FOV from an image. Only pixels with actual signal are considered.

## Input

**file\_name:** str

name of the file to analyse

**ext:** int default=1, optional

extension where the data and WCS info are located. Defaults to 1.

**dtype:** str default='image', optional

type of file to be analyzed. It can be either image or cube. Defaults to image.

**returns**

**SkyCoord** – Coordinate of the center of the FOV

**rtype**

astropy.coordinates.SkyCoord

`pymusepipe.util_image.get_centre_from_pixtable(pixtable_name)`

Get the center of the FOV from pixtables

## Input

**pixtable\_name:** str

name of the pixtable

**returns**

**SkyCoord** – Coordinates of the center of the field

**rtype**

astropy.coordinates.Skycoord

`pymusepipe.util_image.get_flux_range(data, border=15, low=2, high=98)`

Get the range of fluxes within the array by looking at percentiles.

## Input

**data:** 2d array

Input array with signal to process

**low, high:** two floats (10, 99)

Percentiles to consider to filter

**returns**

**lperc, hperc** – Low and high percentiles

**rtype**

2 floats

`pymusepipe.util_image.get_normfactor(array1, array2, median_filter=True, border=0, convolve_data1=0.0, convolve_data2=0.0, chunk_size=10, threshold=0.0, add_background1=0)`

Get the normalisation factor for shifted and projected images. This function only consider the input images given by their data (numpy) arrays.

## Input

array1: 2d np.array array2: 2d np.array

Input arrays. Should be the same size

**median\_filter: bool**

If True, will median filter

**convolve\_muse: float [0]**

Will convolve the image with index nima with a gaussian with that sigma. 0 means no convolution

**convolve\_reference: float [0]**

Will convolve the reference image with a gaussian with that sigma. 0 means no convolution

**border: int**

Number of pixels to crop

**threshold: float [None]**

Threshold for the input image flux to consider

### returns

- **data** (2d array)
- **refdata** (2d array) – The 2 arrays (input, reference) after processing
- **polypar** (the result of an ODR regression)

```
pymusepipe.util_image.get_polynorm(array1, array2, chunk_size=15, threshold1=0.0, threshold2=0,
                                   percentiles=(0.0, 100.0), sigclip=0)
```

Find the normalisation factor between two arrays.

Including the background and slope. This uses the function regress\_odr which is included in align\_pipe.py and itself makes use of ODR in scipy.odr.ODR.

### Parameters

- **array1** (2D np.array) –
- **array2** (2D np.array) – 2 arrays (2D) of identical shapes
- **chunk\_size** (int) – Default value = 15
- **threshold1** (float) – Lower threshold for array1 (Default value = 0.)
- **threshold2** (float) – Lower threshold for array2 (Default value = 0)
- **percentiles** (list of 2 floats) – Percentiles (Default value = [0., 100.])
- **sigclip** (float) – Sigma clipping factor (Default value = 0)

### Returns

**result** – Result of the regression (ODR)

### Return type

python structure

```
pymusepipe.util_image.group_exposures_per_pointing(list_files, target_path="", limit=10.0,
                                                    unit=Unit('arcsec'), ext=1, dtype='image')
```

Separate a list of files in pointings based on their proximity.



This function assign each file to a pointing. Pointings are defined as groups of exposures whose distance between the centers falls within a certain limit. Once the groups of exposures have been defined, they are sorted, and then a pointing number starting from 1 is assigned to all of them. Some info on the average std of the separation between exposures can be optionally computed.

## Input

### **list\_files:** list

list of files to be reorganized in pointings

### **target\_path:** str default=""

path of the target files

### **limit:** float default=10

maximum separation for files to belong to the same pointing

### **unit:** astropy unit default=u.arcsec

Unit of spatial distance (e.g., astropy.unit.arcsec)

### **ext:** int default=1, optional

header extension where the WCS information is located.

### **dtype:** str default 'image', optional

type of file to be analyzed. It can be pixtable, image or cube. Defaults to image.

## returns

- **Pointing dictionary** (*Dict of [int, list]*) – Dictionary grouping the input files by pointing. The keys of the dictionary are the pointing numbers, and to each pointing a list of filenames is associated.
- **Diagnostic dictionary** (*Dict of [int, list], only if diagnostics*) – Dictionary containing basic information on the distance between exposures belonging to the same pointing. For each pointing, the mean and std of the distance with respect to a reference exposure is reported.

`pymusepipe.util_image.group_xy_per_fielddofview(center_dict, limit=<Quantity 10. arcsec>)`

Group exposures in pointings based on their proximity.

## Input

### **center\_dict:** dict

Dictionary containing a list of filenames and their coordinates.

### **limit:** Quantity default=10\*u.arcsec, optional

maximum separation for files to belong to the same pointing. Defaults to 10\*u.arcsec.

Returns: Dict: [int, list]

Dictionary grouping the input files by pointing. The keys of the dictionary are the pointing numbers, and to each pointing a list of filenames is associated.

`pymusepipe.util_image.mask_point_sources(ima, fwhm=3, mask_radius=30.0, brightest=5, sigma=3.0, verbose=False)`

Find and mask point sources in an image by adding NaN

## Input

**ima: ndarray**

Image to mask

**fwhm: float**

guess for the FWHM in pixel of the PSF. Defaults to 3.

**mask\_radius: float**

Radius in pixels to mask around sources

**brightest: int**

Maximum number of bright stars to mask. Defaults to 5.

**sigma: float**

Sigma to clip the image

verbose: bool

**returns**

**ima** – with NaN where the mask applied

**rtype**

np.array

`pymusepipe.util_image.my_linear_model(b, x)`

Linear function for the regression.

## Input

**b**

[1D np.array of 2 floats] Input 1D polynomial parameters (0=constant, 1=slope)

**x**

[np.array] Array which will be multiplied by the polynomial

**rtype**

An array =  $b[1] * (x + b[0])$

`pymusepipe.util_image.prepare_image(data, median_filter=True, sigma=0.0, border=0)`

Median filter plus convolve the input image

## Input

**data: 2D np.array**

Data to process

**median\_filter: bool**

If True, will median filter

**convolve float [0]**

Will convolve the data with this gaussian width (sigma) 0 means no convolution

**returns**

**data**

**rtype**

2d array

`pymusepipe.util_image.regress_odr(x, y, sx, sy, beta0=(0.0, 1.0), percentiles=(0.0, 100.0), sigclip=0.0)`

Return an ODR linear regression using `scipy.odr.ODR`

**Parameters**

- **x** – numpy.array
- **y** – numpy.array Input array with signal
- **sx** – numpy.array
- **sy** – numpy.array Input array (as x,y) with standard deviations
- **beta0** – list or tuple of 2 floats Initial guess for the constant and slope
- **percentiles** – tuple or list of 2 floats Two numbers providing the min and max percentiles
- **sigclip** – float sigma factor for sigma clipping. If 0, no sigma clipping is performed

**Returns**

result of the ODR analysis

**Return type**

result

`pymusepipe.util_image.scan_filenames_from_folder(folder="", prefix="", suffix="", ext='fits', **kwargs)`

Scan a given folder and look for a set of filenames that could enter a pointing table. Those names are decrypted following a given scheme (extracting tpls, expo, dataset)

**Input****folder: str default=""**

Name of the folder to scan

**prefix: str default=""**

Prefix to be used to filter the filenames

**suffix: str default=""**

End of the word before the stem (extension)

**ext: str default='fits'**

Extension

**returns**

filename\_table

**rtype**

astropy QTable with columns 'filename' 'tpls' 'dataset' 'expo'

`pymusepipe.util_image.scan_filenames_from_list(list_files, **kwargs)`

Extract values of dataset, tpls, expo from a list of names

## Input

list\_files: list of str kwargs: additional keywords including

str\_dataset: str ndigits: int filtername: str

### rtype

QTable including filenames, tpls, dataset, expo

`pymusepipe.util_image.select_spaxels(maskdict, maskname, x, y)`

Selecting spaxels defined by their coordinates using the masks defined by Circle or Rectangle Zones

## pymusepipe.util\_pipe module

MUSE-PHANGS utility functions for pymusepipe

**class** `pymusepipe.util_pipe.ExposureInfo(targetname, dataset, tpl, nexpo)`

Bases: `object`

**class** `pymusepipe.util_pipe.TimeStampDict(description="", myobject=None)`

Bases: `OrderedDict`

Class which builds a time stamp driven dictionary of objects

**create\_new\_timestamp**(myobject=None)

Create a new item in dictionary using a time stamp

**delete\_timestamp**(tstamp=None)

Delete a key in the dictionary

`pymusepipe.util_pipe.abspath(path)`

Normalise the path to get it short but absolute

`pymusepipe.util_pipe.add_key_dataset_expo(imaname, iexpo, dataset)`

Add dataset and expo number to image

## Input

imaname: str iexpo: int dataset: int

`pymusepipe.util_pipe.add_string(text, word='_', loc=0)`

Adding string at given location Default is underscore for string which are not empty.

## Input

text (str): input text word (str): input word to be added loc (int): location in 'text'. [Default is 0=start]

If None, will be added at the end.

### rtype

Updated text

`pymusepipe.util_pipe.analyse_musemode(musemode, field, delimiter='-')`

Extract the named field from the musemode

## Input

**musemode: str**

Mode of the MUSE data to be analysed

**field: str**

Field to analyse ('ao', 'field', 'lambda\_range')

**delimiter: str**

Character to delimit the fields to analyse

**returns**

**val** – Value of the field which was analysed (e.g., 'AO' or 'NOAO')

**rtype**

str

`pymusepipe.util_pipe.append_file(filename, content)`

Append in ascii file

`pymusepipe.util_pipe.append_value_to_dict(mydict, key, value)`

Append a value to key within a given dictionary. If the key does not exist it creates a list of 1 element for that key

## Input

mydict: dict key: value:

**rtype**

Updated dictionary

`pymusepipe.util_pipe.build_dict_datasets(data_path="", str_dataset='OB', ndigits=3)`

Build a dictionary of datasets for each target in the sample

## Input

**data\_path: str**

Path of the target data

**str\_dataset: str default=default\_str\_dataset**

Prefix string for datasets (see config\_pipe.py)

**ndigits: int default=default\_ndigits**

Number of digits to format the name of the dataset (see config\_pipe.py)

**returns**

**dict\_dataset**

**rtype**

dict

`pymusepipe.util_pipe.build_dict_exposures(target_path="", str_dataset='OB', ndigits=3, show_pointings=False)`

Build a dictionary of exposures using the list of datasets found for the given dataset path

## Input

**target\_path: str**

Path of the target data

**str\_dataset: str**

Prefix string for datasets

**ndigits: int**

Number of digits to format the name of the dataset

**returns**

**dict\_expo** – Dictionary of exposures in each dataset

**rtype**

dict

`pymusepipe.util_pipe.check_filter_list(filter_list)`

`pymusepipe.util_pipe.create_time_name()`

Create a time-link name for file saving purposes

Return: a string including the YearMonthDay\_HourMinSec

`pymusepipe.util_pipe.filter_list_to_str(filter_list)`

`pymusepipe.util_pipe.filter_list_with_suffix_list(list_names, included_suffix_list=[],  
excluded_suffix_list=[], name_list="")`

Filter a list using suffixes (to exclude or include)

## Input

list\_names: list of str included\_suffix\_list: list of str excluded\_suffix\_list: list of str name\_list: str default=""

`pymusepipe.util_pipe.formatted_time()`

Return: a string including the formatted time

`pymusepipe.util_pipe.get_dataset_name(dataset=1, str_dataset='OB', ndigits=3)`

Formatting for the dataset/pointing names using the number and the number of digits and prefix string

## Input

**dataset: int**

Dataset (or Pointing) number

**str\_dataset: str**

Prefix representing the dataset (or pointing)

**ndigits: int**

Number of digits to be used for formatting

**rtype**

string for the dataset/pointing name prefix

`pymusepipe.util_pipe.get_dataset_tpl_nexpo(filename, str_dataset='OB', ndigits=3, filename=None)`

Get the tpl and nexpo from a filename assuming it is at the end of the filename

### Input

**filename: str**  
Input filename

**returns**  
**tpl, nexpo**

**rtype**  
str, int

`pymusepipe.util_pipe.get_list_datasets(target_path="", str_dataset='OB', ndigits=3, verbose=False)`

Getting the list of existing datasets for a given target path

### Input

**target\_path: str**  
Path of the target data

**str\_dataset: str**  
Prefix string for datasets

**ndigits: int**  
Number of digits to format the name of the dataset

**returns**  
**list\_datasets**

**rtype**  
list of int

`pymusepipe.util_pipe.get_list_exposures(dataset_path="", object_folder='Object')`

Getting a list of exposures from a given path

### Input

**dataset\_path: str**  
Folder name where the dataset is

**returns**  
**list\_expos**

**rtype**  
list of int

`pymusepipe.util_pipe.get_list_reduced_pixtables(target_path="", list_datasets=None, suffix="", str_dataset='OB', ndigits=3, **kwargs)`

Provide a list of reduced pixtables

## Input

**target\_path: str**

Path for the target folder

**list\_datasets: list of int**

List of integers, providing the list of datasets to consider

**suffix: str**

Additional suffix, if needed, for the names of the PixTables.

`pymusepipe.util_pipe.get_list_targets(folder='')`

Getting a list of existing targets given path. This is done by simply listing the existing folders. This may need to be filtered.

## Input

**folder: str**

Folder name where the targets are

**returns**

**list\_targets**

**rtype**

list of str

`pymusepipe.util_pipe.get_pointing_name(pointing=1, str_pointing='P', ndigits=3)`

Formatting for the names using the number and the number of digits and prefix string

## Input

**pointing: int**

Pointing number

**str\_pointing: str**

Prefix representing the pointing

**ndigits: int**

Number of digits to be used for formatting

**rtype**

string for the dataset/pointing name prefix

`pymusepipe.util_pipe.get_tpl_nexpo(filename)`

Get the tpl and nexpo from a filename assuming it is at the end of the filename



## Input

**filename:** str

Input filename

**returns**

**tpl, nexpo**

**rtype**

str, int

`pymusepipe.util_pipe.lower_allbutfirst_letter(mystring)`

Lowercase all letters except the first one

`pymusepipe.util_pipe.lower_rep(text)`

Lower the text and return it after removing all underscores

**Parameters**

**text** (*str*) – text to treat

**Returns**

updated text (with removed underscores and lower-cased)

`pymusepipe.util_pipe.merge_dict(dict1, dict2)`

Merging two dictionaries by appending keys which are duplicated

## Input

dict1: dict dict2: dict

**returns**

**dict1** – merged dictionary

**rtype**

dict

`pymusepipe.util_pipe.normpath(path)`

Normalise the path to get it short

`pymusepipe.util_pipe.print_debug(text, **kwargs)`

Print debugging information

## Input

text: str pipe: musepipe [None]

If provided, will print the text in the logfile

`pymusepipe.util_pipe.print_endline(text, **kwargs)`

`pymusepipe.util_pipe.print_error(text, **kwargs)`

Print error information

## Input

text: str pipe: musepipe [None]

If provided, will print the text in the logfile

`pymusepipe.util_pipe.print_info(text, **kwargs)`

Print processing information

## Input

text: str pipe: musepipe [None]

If provided, will print the text in the logfile

`pymusepipe.util_pipe.print_warning(text, **kwargs)`

`pymusepipe.util_pipe.reconstruct_filter_images(cubename, filter_list='white,Johnson_B,Johnson_V,Cousins_R,SDSS_g,SDSS_r,SDSS_i', filter_fits_file='filter_list.fits')`

Reconstruct all images in a list of Filters cubename: str

Name of the cube

**filter\_list: str**

List of filters, e.g., “Cousins\_R,Johnson\_I” By default, the default\_filter\_list from pymusepipe.config\_pipe

**filter\_fits\_file: str**

Name of the fits file containing all the filter characteristics Usually in filter\_list.fits (MUSE default)

`pymusepipe.util_pipe.safely_create_folder(path, verbose=True)`

Create a folder given by the input path This small function tries to create it and if it fails it checks whether the reason is that it is not a path and then warn the user

## Input

path: str verbose: bool

## Creates

A new folder if the folder does not yet exist

## pymusepipe.version module

Copyright (c) 2016-2019 Eric Emsellem <[eric.emsellem@eso.org](mailto:eric.emsellem@eso.org)>

All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
3. Neither the name of the copyright holder nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS “AS IS” AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

## Module contents

Copyright (C) 2017 ESO/Centre de Recherche Astronomique de Lyon (CRAL) print pymusepipe.\_\_LICENSE\_\_ for the terms of use

This package is a wrapper around the MUSE pipeline commands to reduce muse raw data frames. It includes modules for aligning and convolving the frames. It also has some basic routines wrapped around mpdaf, the excellent python package built around the MUSE PIXTABLES and reduced data.



## INDICES AND TABLES

- `genindex`
- `modindex`
- `search`



## PYTHON MODULE INDEX

### p

- `pymusepipe`, 79
- `pymusepipe.align_pipe`, 10
- `pymusepipe.check_pipe`, 26
- `pymusepipe.combine`, 26
- `pymusepipe.config_pipe`, 31
- `pymusepipe.create_sof`, 31
- `pymusepipe.cube_convolve`, 31
- `pymusepipe.emission_lines`, 35
- `pymusepipe.graph_pipe`, 35
- `pymusepipe.init_musepipe`, 38
- `pymusepipe.mpdaf_pipe`, 38
- `pymusepipe.musepipe`, 47
- `pymusepipe.prep_recipes_pipe`, 49
- `pymusepipe.recipes_pipe`, 53
- `pymusepipe.target_sample`, 55
- `pymusepipe.util_image`, 60
- `pymusepipe.util_pipe`, 72
- `pymusepipe.version`, 78